



Europäisches  
Patentamt

European  
Patent Office

Office européen  
des brevets

REC'D 26 MAY 2004

WIPO

PCT

Bescheinigung

Certificate

Attestation

Die angehefteten Unterlagen stimmen mit der ursprünglich eingereichten Fassung der auf dem nächsten Blatt bezeichneten europäischen Patentanmeldung überein.

The attached documents are exact copies of the European patent application described on the following page, as originally filed.

Les documents fixés à cette attestation sont conformes à la version initialement déposée de la demande de brevet européen spécifiée à la page suivante.

Patentanmeldung Nr. Patent application No. Demande de brevet n°

03368039.8

**PRIORITY  
DOCUMENT**  
SUBMITTED OR TRANSMITTED IN  
COMPLIANCE WITH RULE 17.1(a) OR (b)

Der Präsident des Europäischen Patentamts;  
Im Auftrag

For the President of the European Patent Office

Le Président de l'Office européen des brevets  
p.o.

R C van Dijk



Anmeldung Nr:  
Application no.: 03368039.8  
Demande no:

Anmeldetag:  
Date of filing: 18.04.03  
Date de dépôt:

Anmelder/Applicant(s)/Demandeur(s):

INTERNATIONAL BUSINESS MACHINES CORPORATION

Armonk, NY 10504  
ETATS-UNIS D'AMERIQUE

Bezeichnung der Erfindung/Title of the invention/Titre de l'invention:  
(Falls die Bezeichnung der Erfindung nicht angegeben ist, siehe Beschreibung.  
If no title is shown please refer to the description.  
Si aucun titre n'est indiqué se référer à la description.)

System and method in a data table for managing deletion operations in recursive  
scalable template instances

In Anspruch genommene Priorität(en) / Priority(ies) claimed / Priorité(s)  
revendiquée(s)  
Staat/Tag/Aktenzeichen/State/Date/File no./Pays/Date/Numéro de dépôt:

Internationale Patentklassifikation/International Patent Classification/  
Classification internationale des brevets:

G06F17/20

Am Anmeldetag benannte Vertragstaaten/Contracting states designated at date of  
filing/Etats contractants désignées lors du dépôt:

AT BE BG CH CY CZ DE DK EE ES FI FR GB GR HU IE IT LU MC NL  
PT RO SE SI SK TR LI

## SYSTEM AND METHOD IN A DATA TABLE FOR MANAGING DELETION OPERATIONS IN RECURSIVE SCALABLE TEMPLATE INSTANCES

### *Technical Field of the invention*

The present invention relates to the field of information processing by digital computers, more particularly to a method and system, in a data table, preferably in an electronic spreadsheet, for managing deletion operations in recursive scalable template instances.

### *Background art*

One essential value of electronic spreadsheets is to organize data into columns and rows, while automating tedious calculations. A typical, common, and valuable example of such a set of data organized into columns and rows is a range of cells. Even if a range of cells receives a formal and strict definition within electronic spreadsheet environments, it is flexible enough so that information can be included in either a single range of cells or in a set of several ranges of cells. Ranges of cells therefore are quite useful objects. A range of cell can be defined and processed as a whole entity. For example it can be copied from one place to another place within the spreadsheet or from one spreadsheet file to another spreadsheet file. Ranges of cells are widely used in applications developed in the field of electronic spreadsheets. Most often, the ranges of cells are arranged according to some kind of structure, thus becoming structured ranges of cells. The contents of each cell is defined within an element, where an element is defined as a row of a structured range of cells, and then the same kind of element is repeated a certain number of times, to store/process a variable number of information pieces. Most of the time, several instances of similar structured ranges of cells are used. In the current context where no other tool is really available, instances of such similar structured ranges of cells are frequently created through cut/copy and paste operations. In order to keep a high level of intellectual control over growing quantities of information, human being needs to organize or structure this information. The hierarchical model is often used, because allowing nested structures. A typical and well known example of such a hierarchical structure is the directory tree of computer Operating Systems, such as DOS or Microsoft Windows. The root directory may contain files and/or a number of directories, which may themselves contain files and/or a number of directories, which may themselves contain files and/or a number of directories, etc. Recursivity help structure the information and maintain intellectual control over it. This need for recursivity applies as well, in spreadsheet environment to structured ranges of cells. When several instances of structured ranges of cells are defined and used in an electronic spreadsheet file, they are often themselves structured according to a specific superstructure arrangement or "array of structured ranges of cells" which can be duplicated between different electronic spreadsheet files or even within a single electronic spreadsheet file. Within such an array of structured ranges of cells, it is common to find several structured ranges of cells which follow the same intermediate superstructure, and also some other structured ranges of cells following other intermediate superstructures. The array of structured ranges of cells may then be viewed as a set of aggregated intermediate superstructures of structured ranges of cells. In the current context of conventional electronic spreadsheets, instances of such arrays of structured ranges of cells are frequently created through cut/copy and paste operations.

**Creating a new instance of a structured range of cells is complex and lengthy,** particularly because a conventional range of cells shows strong limitations :

- (i) structure information (such as number of columns, number of rows), format information (such as font style, color or border), and contents information (such as formulas or raw - or informative - data) are mixed,
- (ii) the size of the range of cell is fixed at a given instant.

Therefore, when a spreadsheet user wants to create another range of cells with an identical structure, he/she needs to perform successively several operations. He/she needs to :

1. copy-paste an existing structured range of cells,

2. distinguish between areas containing raw - or informative - data and areas containing generic content such as formulas,
3. empty the copied structured range of cells of the copied raw data while trying to keep the structure, format and generic contents,
- 5 4. adjust the size of the structured copied range of cells to his new needs.
5. eventually, fill the raw data area with default values, in order to ease subsequent data entry.

Furthermore, before copying and pasting a structured range of cells, the user must prepare the place for the copied structured range of cells, with the risk of overwriting, and therefore  
 10 losing the preexisting information at the destination location. This chain of operations rapidly becomes tedious, lengthy and prone to error, especially when manipulated structured ranges of cells increase in size and complexity.

**Updating a structured range of cells is also very often complex, lengthy and prone to error.** Such updates include additions of new elements and modifications of existing  
 15 elements. Several types of modifications can be performed without any specific problem in an electronic spreadsheet environment. However, this is not the case for some modifications, for instance for insertions. For example, if a row is added by means of a conventional function such as the spreadsheet row insertion method, the created row will be empty. This means that the value for every cell of every element needs to be entered.  
 20 Entering data or executing copy/paste operations represents an important workload for the user, while the content of each element is known to a certain extent, and should follow the general structure of the structured range of cells. Moreover, normal spreadsheet functions such as the row insertion function may jeopardize the contents of some neighbour elements. A good example of an insertion jeopardising neighbour elements is the insertion of a row in  
 25 a range of cells in which, on every row, a cell such as C17 or more generally (Cn), is pointing to a cell in the previous row, through a formula such as C16+B17, or more generally (Cn-1)+(Bn). After row insertion between rows 16 and 17, the formula in cell C18 becomes C16+B18 instead of the generic formula C17+B18, or more generally after row insertion between rows (n-1) and (n), the formula in cell (Cn+1) becomes (Cn-1)+(Bn+1) instead of  
 30 the generic formula (Cn)+(Bn+1). As a second exemple, there are cases where modifications must be done consistently throughout the structured range of cells. Today, this can only be done using specific copy-paste operations applied to the exact area to be modified. This may prove to be very difficult, especially when manipulated structured ranges of cells increase in size and complexity.

**Deleting an element of a structured range of cells is an operation prone to error.** As a matter of fact, normal spreadsheet functions such as the row deletion function may jeopardize the contents of some neighbour elements, leading to unresolved references (#REF results) or, even worse to wrong formulas that may be difficult to identify. Solving this problem requires additional "context intelligence", taking into account the structure of the  
 40 structured range of cells in which the element deletion occurs. Another need appears at the time the user invokes the conventional Delete function after selection in the spreadsheet of one or a plurality of cells. If the selection belongs to a structured range of cells, calling the Delete function by means of a menu or by pressing the "Delete" key, leaves room to ambiguity as to what the user wants to perform. Removing this ambiguity can only be done  
 45 today by selecting the exact area to be deleted, which may prove to be very difficult, especially as manipulated structured ranges of cells increase in size and complexity. Solving this problem requires additional "context intelligence" to detect this situation, take advantage of the structure of the structured range of cells and offer the relevant choice to the user.

**When recursivity is involved, creating a new instance of an array of structured ranges of cells is even more complex and lengthy,** particularly because an array of structured  
 50 range of cells involves a twofold level of structure:

- At the lower level a set of multiple, and even different, instances of structured ranges of cells must be created. As previously mentioned, this operation is itself complex, lengthy and prone to error due to the limitations of conventional ranges of cells.



- At the higher level, the creation of an instance of an array of structured range of cells would require that the spreadsheet user carry on several operations:

1. Identify an existing instance of an array of structured ranges of cells, used as a reference for creating the new instance.
2. Prepare the place, at the destination location, to hold the new instance, at the risk of possibly overwriting, and then loosing, any pre-existing information.
3. Copy-Paste the reference instance of the array of structured range of cells onto the destination location.
4. Adjust the structure of the newly created instance of an array of structured ranges of cells to his/her new needs, by either deleting or introducing within the array one or several intermediate superstructures of instances of structured ranges of cells.
5. Clean the content of each instance of structured ranges of cells comprised within the array.
6. Eventually fill each instance of structured ranges of cells with the relevant default values.

**Deleting an object comprised in an instance of an array of structured ranges of cells is an operation prone to error.** Besides the aforementioned risk of creating unresolved references when individual cells or ranges of cells are deleted, the conventional tools available in electronic spreadsheet environments are not keen to assist the spreadsheet user when a deletion operation is invoked after selection of a range of cells, in a recursive structure. Indeed if such a selected range of cells belongs to an instance of an array of structured ranges of cells, the scope of the deletion operation remains ambiguous: either deleting the contents of the IN fields belonging to the selected range of cells, or deleting the elements of the instance of the structured range of cells overlapping with the selected range of cells, or deleting the instances of structured ranges of cells overlapping with the selected range of cells, or even deleting the whole instance of the array of structured ranges of cells comprising the selected range of cells. To remove this ambiguity, the spreadsheet user has to carefully identify and then select the exact relevant range of cells so that the deletion operation exactly matches his needs. When the array of structured ranges of cells becomes large and complex, the previous operation becomes clearly difficult and prone to error. Solving this problem requires further additional "context intelligence" to detect this situation, take advantage of the twofold level of structure of the array of structured ranges of cells and offer the relevant choice to the user. US Patent 5,033,009 entitled "System for generating worksheet files for electronic spreadsheets" Steven J. Dubnoff, March 3rd, 1989, is an interesting document of prior art. This invention develops the concepts of pattern data and variable data that may be integrated to generate a worksheet file through a worksheet file generator. However, this invention shows many limitations preventing it from solving the set of issues presented here above and, in particular :

- It aims at producing a new output spreadsheet from a set of two input files, while there is a need, within a user application environment, to create and manipulate new entities within an existing electronic spreadsheet file, that the user is familiar with.
- It contains no mechanism allowing the direct update of the output spreadsheet, other than the regular spreadsheet tool.
- It contains no capability to manipulate within the same spreadsheet file, a variable number of different structures and a variable number of instances of each of those structure. The granularity is limited to the spreadsheet file, while the required granularity is that of a structured range of cells.
- The so called "file format specification" really mixes structure information (such as number and relative position of columns and rows), presentation information (such as font, color, background, etc.), contents information (such as formulas, etc.).

#### **Summary of the invention**

As defined in independent claims, the present invention is directed to a method, system and program, in a multi-dimensional electronic data table comprising a plurality of data,

- preferably a spreadsheet, for managing deletion operations in a recursive scalable template instance; a recursive scalable template instance comprising a variable number of contiguous recursive element instances ordered and aligned along a first data table dimension and structured according to a recursive scalable template; said recursive scalable template comprising a recursive element including one or a plurality of scalable templates; each recursive element instance having a variable size along said first data table dimension and a same size along a second data table dimension; a recursive element instance comprising one or a plurality of scalable template instances; each scalable template instance of each recursive element instance being aligned along said first data table dimension; each scalable template instance within each recursive element instance being aligned along a second data table dimension; a scalable template instance comprising a variable number of elements structured according to a scalable template; an element being defined as a range of data; a range of data comprising one or a plurality of data. The method comprises the steps of:
- 15 • detecting a delete command for deleting one or a plurality of contiguous elements selected in a scalable template instance of a recursive element instance;
  - identifying :
    - the scalable template instance where to delete said one or a plurality of selected elements;
    - 20 • the one or plurality of selected elements, in the scalable template instance, to delete;
    - the scalable template associated with said scalable template instance;
    - identifying :
      - the recursive scalable template instance and the recursive element instance comprising the identified scalable template instance;
      - 25 • deleting in the identified scalable template instance, the one or a plurality of selected elements; all remaining elements of the identified scalable template instance remaining contiguous;
      - adjusting the size of the identified recursive element instance along said first data table dimension according to the size of the largest scalable template instance in said recursive element instance; all remaining recursive element instances of the identified recursive scalable template instance remaining contiguous.
      - 30 In a particular embodiment, the method comprises the further steps of :
        - detecting a delete command for deleting in a recursive scalable template instance, one or a plurality of selected contiguous recursive element instances;
        - 35 • identifying :
          - the recursive scalable template instance where to delete said one or a plurality of recursive element instances;
          - the one or plurality of recursive element instances to delete in the recursive scalable template instance;
          - 40 • the recursive scalable template associated with said recursive scalable template instance;
          - deleting in the recursive scalable template instance, the one or a plurality of selected contiguous recursive element instances; all remaining recursive element instances of the identified recursive scalable template instance remaining contiguous.
          - 45 Further embodiments of the invention are provided in the appended dependent claims.

#### Acronyms

The following acronyms will be used for more conciseness:

- EF stands for Element Format
- EP stands for Element Profile
- 50 • MEF stands for Meta-element Format
- MEP stands for Meta-element Profile
- RE stands for Recursive Element
- RME stands for Recursive Meta-Element
- RST stands for Recursive Scalable Template

- **RSTI** stands for Recursive Scalable Template Instance
- **ST** stands for Scalable Template
- **STI** stands for Scalable Template Interface

***Brief description of the drawings***

- 5 • Figure **1A** is a schematic view of a computer system in which the present invention may be embodied.
- Figure **1B** is a schematic view of a software system including an operating system, an application software, and a user interface for carrying out the present invention.
- 10 • Figure **2** shows a preferred spreadsheet user interface, according to the preferred embodiment of the present invention, for managing RST's.
- Figure **3** shows a preferred spreadsheet user interface, according to the preferred embodiment of the present invention, for editing EF's.
- Figure **4** shows a preferred spreadsheet user interface, according to the preferred embodiment of the present invention, for editing EP's.
- 15 • Figure **5** shows a preferred spreadsheet user interface, according to the preferred embodiment of the present invention, for editing ST's.
- Figure **6** shows a preferred spreadsheet user interface, according to the preferred embodiment of the present invention, for editing RST's.
- 20 • Figures **7A, 7B, 7C, 7D, 7E** respectively illustrate the structure of the EF Table (EFT), of the EP Table (EPT), of the ST Table (STT), of a ST Descriptor Table (STDT), of the STI Table (STIT), according to the preferred embodiment of the present invention.
- Figure **7F** gives a graphical illustration of the relationships established between the tables EFT, EPT, STT, STDT, STIT, RET, RSTT, RSTDT, RSTIT and RSTIDT according to the preferred embodiment of the present invention.
- 25 • Figure **8** is a flow chart illustrating a preferred method for managing RST objects according to a preferred embodiment of the present invention.
- Figure **9** is a flow chart illustrating a preferred method for editing EF's and MEF's according to a preferred embodiment of the present invention.
- 30 • Figure **10** is a flow chart illustrating a preferred method for editing EP's and MEP's according to a preferred embodiment of the present invention.
- Figures **11** is a flow chart illustrating a preferred method for editing a ST according to a preferred embodiment of the present invention.
- Figures **12** is a flow chart illustrating a preferred method for editing a RST according to a preferred embodiment of the present invention.
- 35 • Figure **13A** shows a preferred spreadsheet user interface, according to the preferred embodiment of the present invention, for creating STI's.
- Figure **13B** illustrates the ST instantiation, according to a preferred embodiment of the present invention.
- Figure **14A** is a flow chart illustrating a preferred method for instantiating a ST according to a preferred embodiment of the present invention.
- 40 • Figure **14B** is a flow chart illustrating a preferred method for creating a STI according to a preferred embodiment of the present invention.
- Figure **15A** is a flow chart illustrating a preferred method for managing deletion in STI's according to a preferred embodiment of the present invention.
- 45 • Figure **15B** is a flow chart illustrating a preferred method for managing deletion in RSTI's according to a preferred embodiment of the present invention.
- Figures **16A, and 16B** show each a preferred spreadsheet user interface, according to the preferred embodiment of the present invention, for managing deletion in STI's.
- Figure **16C** shows a preferred spreadsheet user interface, according to the preferred embodiment of the present invention, for managing deletion in RSTI's.
- 50 • Figure **17A** illustrates the logical structure of a RSTI, according to the preferred embodiment of the present invention.

- Figure 17B illustrates the logical structure of a RST, according to the preferred embodiment of the present invention.
- Figures 18A and 18B constitute a flow chart illustrating a preferred method for creating RSTI's according to a preferred embodiment of the present invention.
- 5 • Figures 19A, 19B, 19C, 19D, 19E and 19F respectively illustrate the structure of the RE Table (RET), of the RST Table (RSTT), of the RST Manager Table (RSTMT), of a RST Descriptor Table (RSTDT), of the RSTI Table (RSTIT), and of a RSTI Descriptor Table (RSTIDT).
- 10 • Figure 20A shows a preferred spreadsheet user interface, according to the preferred embodiment of the present invention, for creating RSTI's.
- Figure 20B shows a preferred spreadsheet user interface, according to the preferred embodiment of the present invention, for editing RE's.
- Figure 20C is a flow chart illustrating a preferred method for editing RE's in RST's according to a preferred embodiment of the present invention.
- 15 • Figure 21A is a flow chart illustrating a preferred method for computing the number of rows comprised in a STI according to a preferred embodiment of the present invention.
- Figure 21B is a flow chart illustrating a preferred method for computing the number of columns comprised in a STI according to a preferred embodiment of the present invention.

#### *Detailed description of the preferred embodiment*

##### **SYSTEM HARDWARE**

- As shown in FIG. 1A, the present invention may be embodied on a computer system 100 comprising a central processor 101, a main memory 102, an input/output controller 103, a keyboard 104, a pointing device 105 (e.g., mouse, track ball, pen device, or the like), a display device 106, and a mass storage 107 (e.g., hard disk). Additional input/output devices, such as a printing device 108, may be included in the system 100 as desired. As illustrated, the various components of the system 100 communicate through a system bus 110 or similar architecture. In a preferred embodiment, the computer system 100 includes an IBM-compatible personal computer, which is available from several vendors (including International Business Machine - IBM Corporation of Armonk, N.Y.). Illustrated in FIG. 1B, a computer software system 150 is provided for directing the operation of the computer system 100. Software system 150, which is stored in system memory 102 and on disk memory 107, includes a kernel or operating system 151 and a shell or interface 153. One or more application programs, such as application software 152, may be "loaded" (i.e., transferred from storage 107 into memory 102) for execution by the system 100. The system 100 receives user commands and data through user interface 153; these inputs may then be acted upon by the system 100 in accordance with instructions from operating module 151 and/or application module 152. The interface 153, which is preferably a graphical user interface (GUI), also serves to display results, whereupon the user may supply additional inputs or terminate the session. In a preferred embodiment, operating system 151 and interface 153 are Microsoft Win95, available from Microsoft Corporation of Redmond, Wash. Application module 152, on the other hand, includes a spreadsheet notebook of the present invention as described in further detail herein below.

##### **INTERFACE**

- 45 The following descriptions will focus on the presently preferred embodiments of the present invention implementing the user interfaces described in international patent application PCT/EP 02/09483 (IBM's reference FR9 2001 0029) entitled "System and method in an electronic spreadsheet for exporting-importing the content of input cells from a scalable template instance to another" by Aureglia et al.

##### **50 RECURSIVE SCALABLE TEMPLATE MANAGEMENT**

###### **A. Introduction**

The concept of scalable templates (ST's)

Conventional electronic spreadsheets include built-in means allowing the spreadsheet users to easily organize data into columns and rows, while automating tedious calculations. This set of organized data can be included in either a single range of cells or in a set of several ranges of cells. The range of cells is a quite useful, and widely used object in an electronic spreadsheet environment. It can be defined and processed as a whole entity. According to the invention described in international patent application PCT/EP 02/09483 (IBM's reference FR9 2001 0029), systems and methods are available to allow an electronic spreadsheet user to:

- Define a structure, for a range of cells, including :
  - (i) an optional header part made of one or more meta-elements ;
  - (ii) a mandatory body part made of one or more elements ;
  - (iii) an optional footer part made of one or more meta-elements.

The structure of **each** meta-element of the header part may be defined in terms of attributes by a MEF, and in terms of contents by a MEP.

The structure of **all** elements of the body part, may be defined in terms of attributes by an EF, and in terms of contents by an EP.

The structure of **each** meta-element of the footer part may be defined in terms of attributes by a MEF, and in terms of contents by a MEP.

This structure is called a ST. In summary, the ST defines a structure by specifying the number of fields, by referring to a couple of EF and EP that defines all body elements, and, optionally, by referring to one or several couples of MEF and MEP that define each meta-element of the header part or the footer part.

- Manage ST's and underneath defined objects, known as EF's, EP's, MEF's and MEP's.
- Create, or update EF's, MEF's.
- Create, or update EP's, MEP's.
- Create, or update a ST.
- Create a STI abiding by a defined ST.
- Remove one or a plurality of elements from a STI.

The above set of functions is supported by a set of tools :

- the "**RST Manager**" method, or **RSTM** method for short;
- the "**EF Editor**" method, or **EFE** method for short;
- the "**EP Editor**" method, or **EPE** method for short;
- the "**ST Editor**" method, or **STE** method for short;
- the "**ST Instanciator**" method, or **STI** method for short;
- the "**STI Deletion Manager**" method, or **STIDM** method for short.

#### **The concept of Recursive Scalable Templates (RST's)**

Having introduced the concept of ST's and of STI's, the concept of RST's and RSTI's becomes easier to capture. Indeed a RST can be seen as a two level structure. The highest level is logically equivalent to the structure of a ST, as a set of structured RE and RME's which can be logically mapped to element and meta-elements. The recursive nature of a RST appears at the lower structural level, because the RE and RME's are objects which themselves comprise STI's (instead of conventional spreadsheet cells, as it is the case for elements and meta-elements). In other words, a RST is a tiered structure of ST's. When a RST is instantiated, the same similarities can be articulated to describe the structure of the resulting RSTI. At a higher level, a RSTI presents a structure logically equivalent to the structure of a STI, but constituted by container ranges instead of individual cells. Within each container range, a lower level structure is present in the form of STI's. As a result a RSTI can be seen as a STI itself containing STI's in lieu of conventional cells. Such an object was therefore first introduced under the name of "an array of structured ranges of cells". Referring now to FIG 17A and 17B, a simple example of such a RST and RSTI will be used to illustrate the present application.

By referring first to FIG 17B, the RST 2051 named "**RST\_customer**" defines the structure followed by a Network Services Provider to record all the various data corresponding to a

customer receiving networking services. This RST is organized around a structure comprising:

- A header part **2052** where the customer data (such as company name, address, business, contract schedule, etc.) are recorded according to the structure of a ST named "*ST\_cust\_data*", where the customer contact points (such as GEO, CIO, CFO, managers, etc.) are recorded according to the structure of a ST named "*ST\_contacts*", where the contracted service level agreements are recorded according to the structure of a ST named "*ST\_SLA*", and where the customer support team (such as the transition manager, the delivery manager, the solution manager, etc.) is recorded according to the structure of a ST named "*ST\_support\_team*".
- A body part **2053** where is recorded, for each customer resource receiving services from the service provider, the information required to manage this resource (such as location, IP address, configuration file, etc.) according to the structure of a ST named "*ST\_res\_info*", and where is recorded the current problem log for the same resource according to the structure of a ST named "*ST\_pb\_log*".
- A footer part **2054** where is recorded the billing status for this customer, according to the structure of a ST named "*ST\_billing*", and where are recorded the problem statistics for the customer managed resources, according to the structure of a ST named "*ST\_stats*".

By referring then to FIG 17B, the RSTI **2001** follows the structure of the RST **2051** "*RST\_customer*". Indeed it is also organized around a structure comprising a header part **2002**, a body part **2003**, and a footer part **2004**. The header part **2002** contains four STI's which are themselves organized according to the structure of the RST header part **2052**, and which abide by the structures of the ST's "*ST\_cust\_data*", "*ST\_contacts*", "*ST\_SLA*", and "*ST\_support\_team*". The body part **2003** is constituted by three different records **2010**, **2009**, and **2008**, each of them organized according to the structure of the RST body part **2053**, that is comprising two STI's which abide by the structures of the ST's "*ST\_res\_info*", and "*ST\_cpb\_log*". Finally the footer part **2004** contains two STI's which are themselves organized according to the structure of the RST footer part **2054**, and which abide by the structures of the ST's "*ST\_billing*", and "*ST\_stats*".

Most often also, several instances of similar recursively structured ranges of cells are used. Within the logic of our example, as described above and illustrated in FIG 17A, a similar recursively structured range of cells is created for each customer in a new sheet. In the current context of electronic spreadsheet environment, where no other tool is really available, instances of such similar recursively structured ranges of cells are frequently created through cut/copy and paste operations.

We have already described the limitations of conventional tools for creating STI's. The creation of a RSTI is even more difficult and prone to errors due to the twofold structure of a RSTI. Indeed the additional difficulty appearing when manipulating such recursive objects is to determine the structural level at which should occur a given operation (such as copy-pasting a recursive object, identifying areas containing row data or structure specific data within a recursive object, adjusting the size of a recursive object, emptying some fields within a recursive object, correcting any error resulting from the previous operations applied to a recursive object, and filling default values in some fields within a recursive object). Furthermore, before the copy-paste operation, on the recursively structured range of cells, takes place, the user must prepare the place for the copied recursively structured range of cells, at the destination location, with the risk, if this is not done, of overwriting, and therefore loosing the preexisting information at this location. The chain of operations described above rapidly becomes tedious, lengthy and prone to error, mainly because the size and complexity of recursively structured ranges of cells are quickly reaching the limits of human beings, when using conventional tools. In a preferred embodiment of the present invention, a user-friendly solution to these problems is proposed by allowing the electronic spreadsheet user to:

- Define a superstructure, for a range of cells, including :
  - (i) an optional header part made of one or more RME's ;
  - (ii) a mandatory body part made of one RE's ;
  - (iii) an optional footer part made of one or more RME's.



The structure of **each** RME of the header part is defined as an ordered collection of superstructure fields, each corresponding to a ST. The structure of **all** RE's of the body part, is defined as an ordered collection of superstructure fields, each corresponding to a ST. The structure of **each** RME of the footer part is defined as an ordered collection of superstructure fields, each corresponding to a ST. This superstructure is called a RST. In summary, the RST defines a superstructure by specifying the number of fields, by referring to a RE that defines the body part, and, optionally, by referring to one or several RME's that define the header part and/or the footer part.

- Manage RST's and underneath defined objects, known as RE's and RME's.
- Create, or update RE's.
- Create, or update RME's.
- Create, or update a RST.
- Create a RSTI abiding by a defined RST.

The above set of functions is supported by a set of tools :

- the "**RST Manager**" method, or **RSTM** method for short;
- the "**RE Editor**" method, or **REE** method for short;
- the "**RST Editor**" method, or **RSTE** method for short;
- the "**RST Instanciator**" method, or **RSTI** method for short.

This set of functions is defined in much further details, in the following sections.

In our example, a RST is developed to define the generic structure of the "NSP Customer Repository" and thus to facilitate the creation of several instances of said "NSP Customer Repository". Now referring to FIG 17B, the RST defining the structure of "NSP Customer Repository" :

- (i) Specifies the number of superstructure fields, 2 (two) in our example.
- (ii) Defines the header part of 2052 "NSP Customer Repository", through the following steps :
  - Defining the structure of a first ST "ST\_cust\_data", and of a second ST "ST\_contacts".
  - Defining the structure of a first RME 2058 comprising the two previous ST's.
  - Defining the structure of a third ST "ST\_SLA", and of a fourth ST "ST\_support\_team".
  - Defining the structure of a second RME 2057 comprising the two previous ST's.
- (iii) Defines the body part 2053 of "NSP Customer Repository", through the following steps :
  - Defining the structure of a fifth ST "ST\_res\_info", and of a sixth ST "ST\_pb\_log".
  - Defining the structure of a RE 2056 comprising the two previous ST's.
- (iv) Defines the footer part 2054 of "NSP Customer Repository", through the following steps :
  - Defining the structure of a first ST "ST\_billing", and of a second ST "ST\_stats".
  - Defining the structure of a RME 2055 comprising the two previous ST's.

From the above RST 2051, one or several RSTI's, such as the one illustrated in FIG 17A, can be created, at very limited cost to the user and thus avoiding the many risks for error.

#### **Deleting an object from a RSTI, deleting a RSTI**

Deleting an element of a RSTI also is an operation prone to error. With our example of a "NSP Customer Repository", the spreadsheet user may have to deal for instance with the retirement of a member in the customer support team, or the removal of an existing customer managed resource, or the deletion of a duplicated problem in a problem log. Besides the difficulties inherent to the deletion of existing elements within a STI, as previously discussed, the deletion of existing pieces of information within a RST is even more challenging because:

- Deleted objects may be defined at different structural levels. For instance, the deletion of a retired customer support team member or of a duplicated problem in a problem log would consist in removing an existing element from a defined STI (respectively the "Support Team" and "Problem Log" STI's), whereas the removal of an existing customer

managed resource will ask to delete within the body part 2003 of the RSTI 2001 a pair of STI's "Resource Information" and "Problem Log" according to the structure of the associated RE 2056. Cautious deletion manipulations must be therefore performed by the spreadsheet user as any error will have to be recovered by preserving the two level structure of the RSTI.

The side effect resulting from the deletion of an existing object may be detrimental either at the lower structural level of the RSTI (for instance by corrupting a STI defined as part of the RSTI), or also at the higher structural level by corrupting the organisation of the various STI's which constitute the RSTI. The former case has already been addressed in the description of the deletion operation within a STI. The later case can be illustrated when the spreadsheet user needs to remove an existing customer managed resource at the top of the body part 2003 of the RSTI 2001. In this case the top "Resource Information" STI and the top "Problem Log" STI 2034 must be removed from the RSTI 2001. As the heights of the two removed STI's are not necessarily equal, the result of the deletion operation is that most probably the two lower existing STI's belonging to the body part 2003 will no longer be horizontally aligned, corrupting therefore the superstructure of the RSTI 2001.

In a preferred embodiment of the present invention, a user-friendly solution to these problems is proposed by allowing the electronic spreadsheet user to:

- select what is to be deleted (cells content, or STI element, or RE, or whole RSTI), upon the automatic prompt triggered by calling the conventional Delete function,
- delete, within a RSTI, either the contents of input fields within selected cells, or the contents of input fields within selected elements, or the content of input fields within selected STI, or the whole selected elements, or the selected RE's, while maintaining the overall integrity of the RSTI, or
- delete a whole RSTI.

The above function is called the "**RSTI Deletion Manager**" method, or **RSTIDM** method for short, and is defined in much further details, in the following sections.

## **B. Concepts and Vocabulary**

The purpose of this section is to formalize both some concepts (with associated objects) and some vocabulary defined within the scope of the present invention. In the following descriptions, it is assumed that spreadsheets are in two dimensions (2D), so that tables and structures can be described in a 2D environment. Moreover it is assumed that tables are organized vertically, so that the table headings are on the top of the table instead of being on its left. This allows to significantly clarify the description of the various original concepts, objects, and methods which are part of the present invention, but this does not limit in any way the scope of the invention. In other words, the underneath description can be generalized to environment with either 2D tables organized horizontally or with 3D tables, without departing from the spirit of the present invention.

### **B1. Preliminary Definitions**

**Structured Range of Cells** : a structured range of cells is a range of cells that abides by some kind of structure organizing the data into rows and columns. Columns define fields aimed at containing the same kind of information on each row. Rows define records (or elements).

**Table** : the word table can be used to designate a structured range of cells.

**Field** : a field is a labeled column in a database or table that contains the same kind of information for each record (or element). For example, a customer table may contain fields labeled Name, Address and Tel #.

By extension, in a given record (or element), a given field refers to the cell located at the intersection of the record (or element) and the given field (labeled column).

The above definitions are for a 2D environment where columns define fields and rows define records. They can be transposed in a 2D environment where rows define fields and columns define record. They can also be transposed in a 3D environment, where, for example, sheets define records.



**IN/OUT Cell:** a cell is specified as "IN" cell when assumed to be used for recording user provided information. A cell is specified as "OUT" cell when assumed to be used for producing information (generally obtained through formulas whose arguments refer directly or indirectly to "IN" cells).

## 5 **B2. Object Definitions**

The following objects are defined to help the understanding of the invention.

**Element Format** : an EF is a spreadsheet object defining the structure of an element within a 2 dimensions or a 3 dimensions range of cells, in terms of format attribute :

- 10 • Background attributes (color, pattern, etc...),
- Alignment attributes (horizontal, vertical, text wrapping, alignment across columns, etc...)
- Font attributes (size, color, etc...)
- Line attributes (type, color, etc...)
- Protection of the field
- 15 • and any other conventional format attribute.

**Meta-Element Format** : a MEF is a spreadsheet object defining the structure of a meta-element within a 2 dimensions or a 3 dimensions range of cells, in terms of format attribute :

- 20 • Background attributes (color, pattern, etc...),
- Alignment attributes (horizontal, vertical, text wrapping, cell merging, etc...)
- Font attributes (size, color, etc...)
- Line attributes (type, color, etc...)
- Protection of the field
- and any other conventional format attribute.

25 **Element Profile** : an EP is a spreadsheet object defining the structure of an element within a 2 dimensions or a 3 dimensions range of cells, in terms of content and destination :

- formulas for fields to be computed from data comprised in other fields of the same element, or in other fields of another element or meta-element of the same STI, or even in other fields outside the STI.
- 30 • field default values to be assigned at element creation time.
- destination of the cells (data entry for "IN" cells or data produced for "OUT" cells).

**Meta-Element Profile** : a MEP is a spreadsheet object defining the structure of a meta-element within a 2 dimensions or a 3 dimensions range, in terms of content and destination :

- 35 • formulas for cells to be computed from data comprised in other cells of the same element, or in other cells of another element or meta-element of the same STI, or even in other cells outside the STI.
- cell default values to be assigned at meta-element creation time.
- 40 • destination of the cells (data entry for "IN" cells or data produced for "OUT" cells)

**Scalable Template** (also referred to as "Template" or "ST") : A ST is a spreadsheet object defining the structure of a 2 dimensions or a 3 dimensions range of cells, in terms of {element + meta-elements} layout. The word "scalable" refers to the capability of the ST of defining a given structure for variable size (e.g. ranging from a minimum value to a maximum value) range of cells. The ST defines a structure by :

- 45 • specifying the number of fields,
- by referring to a couple of EF and/or EP that defines each body element, and,
- optionally, by referring to one or several couples of MEF's and/or MEP's.

In a 2 dimensions environment, such MEF's / MEP's are either located above the EF / EP, constituting the ST "header" part, or located below the EF / EP, constituting the ST "footer" part. Either the ST "header" part or the ST "footer" part, or both of them may be empty.

When the element and meta-element references are only constituted by EP's and MEP's, then the ST only carries contents information and can thus be named **Scalable Profiled Template**.

- 5 When the element and meta-element references are only constituted by EF's and MEF's, then the ST only carries format information and can thus be named **Scalable Formatted Template**.

When the element and meta-element references are constituted by any combination of both EP's and EF's, then the ST carries both profile and format information and can thus be named **Scalable Profiled & Formatted Template**.

- 10 **Scalable Template Instance** (also referred to as "Instance" or "scalable instance" or "STI") : A STI is a spreadsheet object abiding by the structure of a defined ST: a scalable formatted template, or a scalable profiled template, or a scalable profiled & formatted template. An STI may be viewed as a heir object of a ST. It contains a variable number of elements (at least one) containing information, in each field, corresponding to the parent structure, and constituting the "body" part, plus optionally one or several meta-elements, as defined by the ST, and constituting the "header" part and the "footer" part of the STI.

- 15 **Element** : An element is a spreadsheet object belonging to a STI, and made of elementary fields abiding either by an EF, or by an EP, or by a couple (EF, EP) found in the parent structure (respectively scalable formatted template, or scalable profiled template, or scalable profiled & formatted template). Without loosing any generality, it is assumed that an element always abides by a couple (EF, EP), where either the EF or the EP can be reduced to a void object.

- 20 **Meta-Element** : A meta-element is a spreadsheet object belonging to an STI, and made of elementary cells abiding either by a MEF, or by a MEP, or by a couple (MEF, MEP). Without loosing any generality, it is assumed that a meta-element always abides by a couple (MEF, MEP), where either the MEF or the MEP can be reduced to a void object.

- 25 **Recursive Element** : A RE is a spreadsheet object belonging to a RST, constituting the body part of the RST, and made of elementary fields used to record the names of ST's. A RE has a structure similar to the structure of an element, but instead of being instantiated as a range of cells, is instantiated as a range of STI's.

**Example** : The RE of the RST 2051, as illustrated in FIG 17B, corresponds to the structure 2056, constituting the body part 2053 of this RST, and made of two fields which respectively contain the name of the ST's "ST\_res\_info" and "ST\_pb\_log".

- 30 **Recursive Meta-element** : A RME is a spreadsheet object belonging to a RST, belonging to the header and/or footer part of the RST, and made of elementary fields used to record the names of ST's. A RME has a structure similar to the structure of a meta-element, but instead of being instantiated as a range of cells, is instantiated as a range of STI's.

- 35 **Example** : A RME of the RST 2051, as illustrated in FIG 17B, corresponds to the structure 2058, belonging to the header part 2052 of this RST, and made of two fields which respectively contain the name of the ST's "ST\_cust\_data" and "ST\_contacts".

- 40 **Recursive Scalable Template** (also referred to as "Recursive Template" or "RST") : A RST is a spreadsheet object defining the superstructure of a 2 dimensions or a 3 dimensions range of cells, in terms of {RE + RME's} layout. The word "scalable" refers to the capability of the RST of defining a given superstructure for variable size (e.g. ranging from a minimum value to a maximum value) range of cells. The RST defines a superstructure by :

- specifying the number of fields,
- by referring to a RE that defines the body part of the RST, and,
- optionally, by referring to one or several RME's.

- 45 In a 2 dimensions environment, such RME's are either located above the RE, constituting the RST "header" part, or located below the RE, constituting the RST "footer" part. Either the RST "header" part or the RST "footer" part, or both of them may be empty.

**Example** : A RST 2051 is illustrated in FIG 17B. It is constituted by a header part 2052, a body part 2053 and a footer part 2054. The header part comprises two RME's 2058 and 2057, both with two fields, and which respectively contain the name of the ST's

"ST\_cust\_data", "ST\_contacts" and "ST\_SLA", "ST\_support\_team". The body part comprises one RE 2056 with two fields which respectively contains the name of the ST's "ST\_res\_info", "ST\_pb\_log". The footer part comprises one RME 2055 with two fields which respectively contains the name of the ST's "ST\_billing", "ST\_stats".

- 5 **Recursive Scalable Template Instance** (also referred to as "Recursive Instance" or "Recursive Scalable Instance" or as RSTI): A RSTI is a spreadsheet object abiding by the structure of a defined RST. A RSTI may be viewed as a heir object of a RST. It contains a variable number of container rows (at least one) containing one or a plurality of STI's, corresponding to the parent RE structure, and constituting the "body" part, plus optionally  
 10 one or several other container rows containing one or a plurality of STI's, corresponding to the parent RME's structure, and constituting the "header" part and the "footer" part of the RSTI.

15 Example: A RSTI 2001 is illustrated in FIG 17A. This RSTI abides by the RST 2051 as illustrated in FIG 17B. It is constituted by a header part 2002, a body part 2003 and a footer part 2004. The header part comprises two container rows 2012 and 2011. The body part comprises three container rows 2010, 2009 and 2008. The footer part comprises one container row 2007. Each container row contains two container ranges, such as the container range 2014 which can be seen as the intersection of the top container row 2012 and of the right container column 2005. Each container range  
 20 contains a STI which abides by the structure of the ST defined as part of the RE or RME member of the RST 2051. For instance the STI 2034 comprised within the container range intersection of the container row 2010 and of the container column 2005 abides by the structure of the ST named "ST\_pb\_log", as defined in the RME 2056 of the RST 2051, and is itself constituted by a header part 2015, a body part 2016 and a footer part  
 25 2017.

**Container rows** : a container row is a spreadsheet object belonging to a RSTI, and corresponding to the range of cells containing the STI's which are structured according to the definition of a RE or of a RME part of the RST that the RSTI abides by. The number of rows of a container row is equal to the number of rows of the highest STI it contains. A  
 30 container row can also be referred to as a recursive element instance. A container row can be seen within a RSTI as equivalent to an element within a STI. Example : The container row 2012 is illustrated in FIG 17A, and corresponds to the range of cells comprising the STI's 2032 and 2013 which are defined within the RSTI 2001. The number of rows of this container row is equal to the number of rows of the STI 2032 which is higher than the STI  
 35 2013.

**Container columns** : a container column is a spreadsheet object belonging to a RSTI, and corresponding to the range of cells containing the STI's which occupy the same superstructure position within the container rows of the RSTI. The number of columns of a container column is equal to the number of columns of the widest STI it contains. Example :  
 40 The container column 2006 is illustrated in FIG 17A, and corresponds to the range of cells comprising the STI's occupying the leftmost position within the RSTI 2001. The number of columns of this container column is equal to the number of columns of the STI 2030 which is the widest STI on the left side of the RSTI 2001.

**Container ranges** : a container range is a spreadsheet object belonging to a RSTI, and corresponding to the intersection of a container row and of a container column. Each container range contains a single STI which occupies the top and leftmost corner. A container range within a RSTI can be seen as equivalent to a single cell within a STI. Example : The container range 2014 is illustrated in FIG 17A, and corresponds to the  
 45 intersection of the container row 2012 and of the container column 2005, both belonging to the RSTI 2001. This container range 2014 contains the STI 2013.

### B3. Notations

The following notation :  $\prod_{i \in S} a_i$  corresponds to the multiplication of the terms  $a_i$ , the index  $i$  belonging to the set  $S$ . The following notation :  $\text{LCM}(\{a_i\}_{i \in S})$  corresponds to the Least

Common Multiplier of the terms  $a_i$ , the index  $i$  belonging to the set  $S$ . If  $S$  is constituted by a single element  $a$ , then  $\text{LCM}(\{a_i\}_{i \in S})$  is equal to  $a$ . The following notation :  $a \text{ Mod } b$  corresponds to the remainder of the division of  $a$  by  $b$  (**Mod** for "Modulo").

### C. Tables used for managing RST objects

- 5 As Introduced in the previous section, the preferred embodiment of the present invention relies on different types of objects for managing RST's. These objects are recorded in different repositories, so that they can be accessed and updated by the different methods which are part of the preferred embodiment of the present invention. Such repositories are referred to as tables:
- 10 • the **EF Table** or **EFT** for short,
  - the **EP Table** or **EPT** for short,
  - the **ST Table** or **STT** for short,
  - The **ST Descriptor Table** or **STDT** for short.
  - The **ST Instanciator Table** or **STIT** for short.
  - 15 • The **RE Table** or **RET** for short.
  - The **RST Table** or **RSTT** for short.
  - The **RST Manager Table** or **RSTMT** for short.
  - The **RST Descriptor Table** or **RSTDT** for short.
  - The **RSTI Table** or **RSTIT** for short.
  - 20 • The **RSTI Descriptor Table** or **RSTIDT** for short.

The **EFT**, **EPT**, **STT**, **STDT**, **STIT**, **RET**, **RSTT**, **RSTDT**, **RSTIT**, and **RSTIDT** tables are saved as part of the spreadsheet disk file on the mass storage 107, whereas the **RSTMT** table is temporarily saved on the main memory 102 and the **RSTEIT** table is saved on spreadsheet export-import files.

#### 25 C1. EF Table

Referring now to FIG. 7A, the **EFT** Table 700 corresponds to a logical simple structure made of several records 701, each of them corresponding to an EF or to a MEF, according to the present invention. Each record includes six fields:

- The "Name" 702 field is used for recording a character string which uniquely identifies the EF or the MEF described by the current record 701.
- 30 • The "Last Change Date" 703 field is used for recording the date of the last update of the EF or the MEF described by the current record 701.
- The "Description Ptr" 704 field is a reference pointing to the memory location where is recorded an illustrative range of cells depicting the EF or MEF described by the current record 701. This memory location can either be on the Mass storage 107, or on the main memory 102, or on other conventional memory repository means, without departing from the spirit of the present invention.
- 35 • The "Row #" 705 field is used for recording the number of rows present in the EF or in the MEF described by the current record 701. This field is relevant for 3D ST's where element or MEF's correspond to 2D structures. In the preferred embodiment of the present invention where 2D ST's are assumed, this field is always filled with the value 1.
- The "Column #" 706 field is used for recording the number of columns present in the EF or in the MEF described by the current record 701.
- 40 • The "Type" 707 field is used for recording different attributes associated to the EF or to the MEF described by the current record 701: this is the "META" attribute 708 specifying if the current record 701 describes an EF or a MEF (with respective values "NO" and "YES"), and the "REFERENCED" attribute 709 specifying through dedicated subfields (709a, 709b, 709c, 709d and 709e) the relationships with other objects. These subfields are described as part of the description of the "REFERENCED" attribute 2240. Conventional techniques can be used for encoding these different attributes in this "Type" field, such as executing bit-wise XOR operations with predefined bit patterns, but any other conventional means could be used instead without departing from the spirit of the invention.
- 50

**C2. EP Table**

Referring now to FIG. 7B, the **EPT** Table 710 corresponds to a logical simple structure made of several records 711, each of them corresponding to an EP or to a MEP, according to the present invention. Each record includes six fields:

- 5 • The "**Name**" 712 field is used for recording a character string which uniquely identifies the EP or the MEP described by the current record 711.
- The "**Last Change Date**" 713 field is used for recording the date of the last update of the EP or the MEP described by the current record 711.
- 10 • The "**Description Ptr**" 714 field is a reference pointing to the memory location where an illustrative range of cells depicting the EP or MEP described by the current record 711 is recorded. This memory location can either be on the Mass storage 107, or on the main memory 102, or on other conventional memory repository means, without departing from the spirit of the present invention.
- 15 • The "**Row #**" 715 field is used for recording the number of rows present in the EP or in the MEP described by the current record 711. This field is relevant for 3D ST's where element or MEP's correspond to 2D structures. In the preferred embodiment of the present invention where 2D ST's are assumed, this field is always filled with the value 1.
- The "**Column #**" 716 field is used for recording the number of columns present in the EP or in the MEP described by the current record 711.
- 20 • The "**Type**" 717 field is used for recording different attributes associated to the EP or to the MEP described by the current record 711: this is the "**META**" attribute 718 specifying if the current record 701 describes an EP or a MEP (with respective values "no" and "yes"), and the "**REFERENCED**" attribute 719 specifying through dedicated subfields (719a, 719b, 719c, 719d and 719e) the relationships with other objects. These subfields are
- 25 described as part of the description of the "**REFERENCED**" attribute 2240. Conventional techniques can be used for encoding these different attributes in this "**Type**" field, such as executing bit-wise XOR operations with predefined bit patterns, but any other conventional means could be used instead without departing from the spirit of the invention.

**C3. ST Table**

Referring now to FIG. 7C, the **STT** Table 720 corresponds to a logical simple structure made of several records 721, each of them corresponding to a ST, according to the present invention. Each record includes six fields:

- 35 • The "**Name**" 722 field is used for recording a character string which uniquely identifies the ST described by the current record 721.
- The "**Last Change Date**" 723 field is used for recording the date of the last update of the ST described by the current record 721.
- 40 • The "**Description Ptr**" 724 field is a reference pointing to the memory location where a description of the ST described by the current record 721 is recorded. This memory location can either be on the mass storage 107, or on the main memory 102, or on other conventional memory repository means, without departing from the spirit of the present invention. This description is structured according to the STDT table 760 illustrated in FIG 7D, that is as an ordered list of couples of names, each couple being made by the name of an element or MEF and by the name of an element or MEP.
- 45 • The "**Min Element #**" 725 field is used to record the minimum number of elements found in each STI abiding by the ST described by the current record 721.
- The "**Max Element #**" 726 field is used to record the maximum number of elements found in each STI abiding by the ST described by the current record 721.
- 50 • The "**Type**" 727 field is used for recording different attributes associated to the ST described by the current record 721: this is the "**META**" attribute 728 which always take the value "no", and the "**REFERENCED**" attribute 729 specifying through dedicated subfields (729a, 729b, 729c, 729d and 729e) the relationships with other objects. These subfields are described as part of the description of the "**REFERENCED**" attribute 2240. Conventional

techniques can be used for encoding these different attributes in this "Type" field, such as executing bit-wise XOR operations with predefined bit patterns, but any other conventional means could be used instead without departing from the spirit of the invention.

#### 5 C4. ST Descriptor Table

Referring now to FIG. 7D, the **STDT** Table 760 corresponds to a logical simple structure made of several couples of element or MEF 765 and of element or MEP 764. This structure is organized into three sub-sets:

- 10 • The optional ST "Header" part 767, made of a variable number (possibly null) of couples like the top couple 761. Each of these couples is constituted by a MEF (column 765) and by a MEP (column 764).
- The mandatory "Body" part 762 made of a single couple constituted by an EF (column 765) and by an EP (column 764).
- 15 • The optional ST "Footer" part 766, made of a variable number (possibly null) of couples like the bottom couple 763. Each of these couples is constituted by a MEF (column 765) and by a MEP (column 764).

#### C5. ST Instanciator Table

20 Referring now to FIG. 7E, the **STIT** Table 750 corresponds to a logical simple structure made of several records 751, each of them corresponding to a STI, according to the preferred embodiment of the present invention. Each record includes six fields:

- The "Address" 752 field is used for locating the STI described by the current record 751: its value corresponds to the conventional character string used to record the address of any range of cells.
- 25 • The "ST" 753 field is used for recording the name of the ST abided by the STI described by the current record 751.
- The "Element #" 754 field is used for recording the number of elements within the STI described by the current record 751.
- The "Critical" 755 field is used for recording if the STI described by the current record 751 is considered as critical. Its content can take the values "YES" or "NO".
- 30 • The "Header Size" 756 field is used for recording the number of meta-elements constituting the Header part of the STI described by the current record 751.
- The "Footer Size" 757 field is used for recording the number of meta-elements constituting the Footer part of the STI described by the current record 751.

#### C6. RE Table

35 Referring now to FIG. 19A, the **RET** Table 2210 corresponds to a logical simple structure made of several records 2211, each of them corresponding to a RE or to a RME, according to the present invention. Each record includes six fields:

- The "Name" 2212 field is used for recording a character string which uniquely identifies the RE or the RME described by the current record 2211.
- 40 • The "Last Change Date" 2213 field is used for recording the date of the last update of the RE or of the RME described by the current record 2211.
- The "Description Ptr" 2214 field is a reference pointing to the memory location where is recorded an illustrative range of cells depicting the RE or the RME described by the current record 2211. This memory location can either be on the Mass storage 107, or on the main memory 102, or on other conventional memory repository means, without departing from the spirit of the present invention.
- 45 • The "Row #" 2215 field is used for recording the number of rows present in the RE or in the RME described by the current record 2211. This field is relevant for 3D RST's where RE's or RME's correspond to 2D structures. In the preferred embodiment of the present invention where 2D RST's are assumed, this field is always filled with the value 1.
- 50 • The "Column #" 2216 field is used for recording the number of columns present in the RE or in the RME described by the current record 2211.



- The "Type" 2217 field is used for recording different attributes associated to the RE or to the RME described by the current record 2211: this is the "META" attribute 2218 specifying if the current record 2211 describes a RE or a RME (with respective values "NO" and "YES"), and the "REFERENCED" attribute 2219 specifying through dedicated subfields (2219a, 2219b, 2219c, 2219d and 2219e) the referenciation relationships with other objects. These subfields are described as part of the description of the "REFERENCED" attribute 2240. Conventional techniques can be used for encoding these different attributes in this "Type" field, such as executing bit-wise XOR operations with predefined bit patterns, but any other conventional means could be used instead without departing from the spirit of the invention.

#### C7. RST Table

Referring now to FIG. 19B, the *RSTT* Table 2220 corresponds to a logical simple structure made of several records 2221, each of them corresponding to a RST, according to the present invention. Each record includes six fields:

- The "Name" 2222 field is used for recording a character string which uniquely identifies the RST described by the current record 2221.
- The "Last Change Date" 2223 field is used for recording the date of the last update of the RST described by the current record 2221.
- The "Description Ptr" 2224 field is a reference pointing to the memory location where a description of the RST described by the current record 2221 is recorded. This memory location can either be on the mass storage 107, or on the main memory 102, or on other conventional memory repository means, without departing from the spirit of the present invention. This description is structured according to the RSTDT table 2250 illustrated in FIG 19D, that is as an ordered list of RME or RE names.
- The "Min Element #" 2225 field is used for recording the minimum number of RE's found in every RSTI abiding by the RST described by the current record 2221.
- The "Max Element #" 2226 field is used for recording the maximum number of RE's found in every RSTI abiding by the RST described by the current record 2221.
- The "Type" 2227 field is used for recording different attributes associated to the RST described by the current record 2221: this is the "META" attribute 2228 which always take the value "NO", and the "REFERENCED" attribute 2229 specifying through dedicated subfields (2229a, 2229b, 2229c, 2229d and 2229e) the relationships with other objects. These subfields are described as part of the description of the "REFERENCED" attribute 2240. Conventional techniques can be used for encoding these different attributes in this "Type" field, such as executing bit-wise XOR operations with predefined bit patterns, but any other conventional means could be used instead without departing from the spirit of the invention.

#### C8. RST Manager Table .

Referring now to FIG. 19C, the *RSTMT* Table 2230 corresponds to a logical simple structure made of several records 2231, each of them corresponding to an object managed by the RST manager, according to the preferred embodiment of the present invention. Each record includes seven fields:

- The "Name" 2232 field is used for recording a character string which uniquely identifies the object described by the current record 2231.
- The "Last Change Date" 2233 field is used for recording the date of the last update of the object described by the current record 2231.
- The "Description Ptr" 2234 field is a reference pointing to the memory location where is recorded a description of the object described by the current record 2231. This memory location can either be on the Mass storage 107, or on the main memory 102, or on other conventional memory repository means, without departing from the spirit of the present invention.
- The "Info Field 1" 2235 field is used for recording a first piece of information associated to the object described by the current record 2231.

- The "Info Field 2" **2236** field is used for recording a second piece of information associated to the object described by the current record **2231**.
- The "Type" **2237** field is used for recording different attributes associated to the object described by the current record **2231**, such as:

- the attribute "META" **2239** previously described for the similar "Type" fields **707**, **717**, **727**, **777**, **2217**, and **2227**, and also two other attributes:
- the attribute "REFERENCED" **2240** which is constituted by 5 (five) subfields, according to the FIG 19C illustrating an example of RSTMT table **2230**:

- The "OWN REFERENCE" (or OR for short) subfield **2240a**. This subfield is a unique prime number assigned when the object described by the record **2231** is created. This prime number is released only when the object described by the record **2231** is deleted.

- The "FILIALION REFERENCE" (or FR for short) subfield **2240b**. This subfield is evaluated according to the following formula, where the F set corresponds to the set of objects constituting the object described by the record **2231**:

$$FR = \prod_{i \in F} OR_i \times LCM(\{FR_i\})_{i \in F}$$

The above formula allows to dynamically link the object described by the record **2231** with the objects constituting it, because any change in the value of one of the factors  $OR_i$  or  $FR_i$  will be automatically reflected into FR. If the F set is empty (for instance when the object described by the record **2231** is an EP, or a MEP, or an EF, or a MEF), then the FR subfield defaults to the value 1 (one).

- The "INSTANCE REFERENCE" (or IR for short) subfield **2240c**. This subfield is initiated to the value 1 (one) when the object described by the record **2231** is created. Afterwards this subfield is multiplied by 2 (two) each time a new instance abiding by this object is created, and is divided by 2 (two) each time an existing instance abiding by this object is deleted.

- The "REFERENCED OBJECT" (or RO for short) subfield **2240d**. This subfield is a Boolean variable specifying if the object described by the record **2231** participates to the definition of another object. For instance an EF, or a MEF, or an EP, or a MEP can participate to the definition of a ST. Similarly a ST can participate to the definition of a RE which can itself participate to the definition of a RST. This subfield is evaluated according to the following formula, where the P set corresponds to the set of objects the type of which follows the type of the object described by the record **2231**, in the hierarchy of RST objects:

$$RO = \text{"YES"} \text{ if } LCM(\{FR_i\})_{i \in P} \bmod OR = 0;$$

$$RO = \text{"NO"} \text{ otherwise.}$$

The above formula allows to dynamically link the object described by the record **2231** with the objects belonging to the P set, because any change in the value of one of the factors  $FR_i$  will be automatically reflected into RO. If the object described by the record **2231** is an EF, or a MEF, or an EP, or a MEP, then the P set corresponds to the set of ST's. If the object described by the record **2231** is a ST, then the P set corresponds to the set or RE's. If the object described by the record **2231** is a RE, then the P set corresponds to the set or RST's. If the object described by the record **2231** is a RST, then the P set is empty (the top of the hierarchy being reached), so that the RO subfield defaults to the value "NO".

- The "SELECTED CHILDREN" (or SC for short) subfield **2240e**. This subfield is a Boolean variable specifying if the object described by the record **2231** participates to the definition of a selected object. This subfield is evaluated according to the following formula, where the S set corresponds to the set of selected objects (having the "SELECTED" attribute **2242** equal to the value "YES"):

$$SC = \text{"YES"} \text{ if } LCM(\{FR_i\})_{i \in S} \bmod OR = 0 \text{ \#OR\# object } \in S;$$

$$SC = \text{"NO"} \text{ otherwise.}$$



The above formula allows to dynamically link the object described by the record **2231** with the selected objects (belonging to the S set), because any change in the value of one of the factors  $FR_i$  or in the S set will be automatically reflected into SC.

- 5 The other "REFERENCED" attributes **709**, **719**, **729**, **780**, **2219**, and **2229**, as defined within the tables EFT **700**, EPT **710**, STT **720**, RSTEIT **770**, RET **2210**, and RSTT **2220**, are based on the same set of five subfields.
- the "SELECTED" attribute **2242** reflecting whether the associated object has been or not selected by the spreadsheet user within the RST Manager Dialog Box **2300**, (with
  - 10     respective values "YES" and "NO"), and also
  - the "NATURE" attribute **2241** reflecting whether the object is a (M)EF, or a (M)EP, or a ST, or a R(M)E, or a RST (with respective values "FORMAT", or "PROFILE" or "TEMPLATE" or "RECELEMENT" or "RECTEMPLATE").

15 Conventional techniques can be used for encoding these different attributes in this "Type" field **2237**, such as executing bit-wise XOR operations with predefined bit patterns, but any other conventional means could be used instead without departing from the spirit of the invention.

- The "Index" **2238** field is used for sorting the *RSTMT* table, as performed by the *RST Manager* method.

#### 20 **C9. RST Descriptor Table**

Referring now to FIG. **19D**, the *RSTDT* Table **2250** corresponds to a logical simple structure made of several names of RE's or RME's **2254**. This structure is organized into three sub-sets:

- The optional RST "Header" part **2256**, made of a variable number (possibly null) of RME names like the top name **2251**.
- The mandatory "Body" part **2252** made of a single RE name.
- The optional RST "Footer" part **2255**, made of a variable number (possibly null) of RME names like the bottom name **2253**.

#### **C10. RSTI Table**

30 Referring now to FIG. **19E**, the *RSTIT* Table **2260** corresponds to a logical simple structure made of several records **2261**, each of them corresponding to a RSTI, according to the preferred embodiment of the present invention. Each record includes six fields:

- The "Address" **2262** field is used for locating the RSTI described by the current record **2261**: its value corresponds to the conventional character string used to record the
- 35     address of any range of cells.
- The "ST" **2263** field is used for recording the name of the RST abided by the RSTI described by the current record **2261**.
- The "Element #" **2264** field is used for recording the number of RE's within the RSTI described by the current record **2261**.
- 40     • The "Critical" **2265** field is used for recording if the RSTI described by the current record **2261** is considered as critical. Its content can take the values "YES" or "NO".
- The "Header Size" **2266** field is used for recording the number of RME's constituting the Header part of the RSTI described by the current record **2261**.
- The "Footer Size" **2267** field is used for recording the number of RME's constituting the
- 45     Footer part of the RSTI described by the current record **2261**.

#### **C11. RSTI Descriptor Table**

Referring now to FIG. **19F**, the *RSTIDT* Table **2270** corresponds to a logical simple structure made of several records **2271**, each of them made of several cells **2272**, each of them corresponding to a STI member of the RSTI, according to the preferred embodiment

50 of the present invention. The *RSTIT* table **2270** is mapped to the structure of the associated RSTI with a top header part **2275** (possibly empty) constituted by one or several records **2271**, with a middle body part **2274** constituted by one or several records **2271**, and with a

bottom footer part 2273 (possibly empty) constituted by one or several records 2271. Each record 2271 comprises one or a plurality of individual cells 2272, the number of which corresponding to the number of STI's per RE. Each record 2272 includes seven fields characterizing a STI member of the RSTI:

- 5 • The "*container\_range*" 2276 field is used for recording the address of the container range hosting the STI described by the record 2272. By referring to the FIG 17A, this field records the address of the container 2014 (intersection of the container row 2012 and of the container column 2005) if the record 2272 describes the STI 2013.
- 10 • The "*container\_col*" 2277 field is used for recording the number of columns of the container range hosting the STI described by the record 2272. By referring to the FIG 17A, this field records the column number 2028 if the record 2272 describes the STI 2013.
- 15 • The "*STI\_col*" 2278 field is used for recording the number of columns of the STI described by the record 2272. By referring to the FIG 17A, this field records the column number 2026 if the record 2272 describes the STI 2013.
- The "*STI\_row*" 2279 field is used for recording the number of rows of the STI described by the record 2272. By referring to the FIG 17A, this field records the row number 2027 if the record 2272 describes the STI 2013.
- 20 • The "*ST\_name*" 2280 field is used to record the name of the ST abided by the STI described by the record 2272.
- The "*container\_row*" 2281 field is used for recording the number of rows of the container range hosting the STI described by the record 2272. By referring to the FIG 17A, this field records the row number 2029 if the record 2272 describes the STI 2013.
- 25 • The "*STIT\_rec\_ptr*" 2282 field is used for pointing, within the *STIT* table 750, to the record 751 describing the STI described by the record 2272.

#### C12. Relationships Between Tables

Referring now to FIG. 7F, some previously introduced tables RSTIT 2260, RSTIDT 2270, RSTT 2220, RSTDT 2250, RET 2210, STIT 750, STT 720, STDT 760, EFT 700 and EPT 710 are presented altogether to illustrate the relationships established between these tables and with either a RSTI RSTI 730 or a STI STI 797. Within this diagram, a solid bold arrow illustrates a pointer based relationship towards a table or a record, a dashed bold arrow illustrates an address based relationship towards a range of cells, a solid unbold arrow illustrates a name based relationship towards an object, and a dashed unbold arrow illustrates a size based relationship towards an object. In the FIG 7F, the pointer based, address based and named relationships are identified by an index represented within a circle, according to the following sequence:

- 30 • Starting with a STI STI 797 made of the three parts "*STI Header*", "*STI Body*" and "*STI Footer*", a first address based relationship j is established between this STI STI 797 and a record 751 of the STIT table 750.
- 40 • A second name based relationship k is then established between this record 751 and a record 721 of the STT table 720. This record 721 corresponds to the ST abided by the STI 797.
- A third pointer based relationship l is established between this record 721 and a STDT table 760 which describes the structure of the ST. Each record of the STDT table 760 corresponds to a pair of an element or MEF name and of an element or MEP name.
- 45 • A fourth name based relationship m is established between the element or MEF name and a record 701 of the EFT table 700.
- A fifth name based relationship n is established between the element or MEP name and a record 711 of the EPT table 710.
- 50 • A sixth pointer based relationship o is established between the record 701 and an illustrative range of cells 798 specifying the format attributes.
- A seventh pointer based relationship p is established between the record 711 and an illustrative range of cells 799 specifying the profile content.

- Starting now with a RSTI 730 made of the three parts "*RSTI Header*", "*RSTI Body*" and "*RSTI Footer*", an eighth address based relationship  $q$  is established between this RSTI 730 and a record 2261 of the RSTIT table 2260.
- 5 • A ninth pointer based relationship  $r$  is established between this record 2261 and a RSTIDT table 2270 which describes the structure of the RSTI 730. Each cell 2272 of the RSTIDT table 2270 comprise several fields 2276, 2277, 2278, 2279, 2280, 2281 and 2282 related to a given STI (like STI 797) member of the RSTI 730.
- 10 • A tenth address based relationship  $s$  is thus established between the 2276 field of the cell 2272 of the RSTIDT table 2270, and the container range comprising the STI STI 797.
- An eleventh pointer based relationship  $jj$  is also established between the 2282 field of the cell 2272 of the RSTIDT table 2270, and the record 751 of the STIT table 750 corresponding to the STI STI 797.
- 15 • A twelfth name based relationship  $jk$  is then established between the record 2261 and a record 2221 of the RSTT table 2220. This record 2221 corresponds to the RST abided by the RSTI 730.
- A thirteenth pointer based relationship  $jl$  is established between this record 2221 and a RSTDT table 2250 which describes the structure of the RST. Each record of the RSTDT table 2250 corresponds to a RE or RME.
- 20 • A fourteenth name based relationship  $jm$  is established between the RE or RME name and a record 2211 of the RET table 2210.
- A fifteenth pointer based relationship  $jn$  is established between the record 2211 and a RE descriptor range of cells 731 containing the names of ST's.
- 25 • A sixteenth name based relationship  $jo$  is established between the RE descriptor range of cells 731 and a record 721 of the STT table 720.
- A similar seventeenth name based relationship  $jp$  is established between the cell 2272 of the RSTIDT table 2270 and a record 721 of the STT table 720.

#### D. Scenarios

30 In contrast to just-described conventional tools, the preferred embodiment of the present invention provides a more powerful, user-friendly and interactive approach for defining and managing ST's, in a form of a collection of methods.

In a preferred embodiment, the present invention is used within a scenario which articulates as a sequence of operations :

- 35 • **1. First Operation : Creation of a STI or of a RSTI**
- The first operation occurs when the spreadsheet user decides, based on some criteria not detailed here, to either create a STI abiding by the structure of a ST or to create a RSTI abiding by the structure of a RST. In a preferred embodiment of the present invention, this operation comprises the following steps:
- 40 • **a. RST Manager:** The spreadsheet user invokes first an original specific command called "**RST Manager**" thanks to conventional means available in spreadsheet environment, such as but not limited to the pointing device 105 or the keyboard 104, in order to visualize through a dedicated user interface any existing EF or MEF or EP or MEP or RE or RME or ST or RST. This RST manager offers different alternatives for further managing these entitles. This can be illustrated with the user interface described with the FIG 2, showing the RST Manager Dialog Box 200, as displayed
- 45 on the display device 106. Within this RST Manager Dialog Box 200, the user can visualize already defined objects (EF's, MEF's, EP's, MEP's, RE's, RME's, ST's and RST's) in the "list boxes" 213, 214 and 202 where are respectively specified the names of the objects, the types of the objects and their last date of update. If a large number of objects have been defined, then the user can navigate among them by clicking with the pointing device 105 either upwards or downwards on the scroll bar 203, so that the objects shown within the list boxes 213, 214 and 202 move back and forth between the top object and the bottom object. In a preferred embodiment of the
- 50

present invention, the objects have been sorted by date of last update, but any other sorting scheme could be also used without departing from the spirit of the invention. Several actions may then be taken by the user.

5 The user can use the pointing device 105 to click on a check box on the left side of the RST Manager-Dialog Box 200 like the check-box 212, in order to either select or  
10 deselect the object whose name is displayed within the list box 213 just on the right of the clicked check box. One or multiple objects can be selected or deselected. List scrolling is of course reflected on the check boxes. Once a selection is performed, the user can use the pointing device 105 to click on the "Delete" push-button 207, if  
15 he/she intends to remove all the selected objects from the list boxes 213, 214 and 202. If there is no other object (either ST or STI or RE or RME or RST or RSTI) referring to at least one of these objects, then they are immediately deleted, so that they do no longer appear on the list boxes 213, 214 and 202. If there exists at least  
20 one other ST or STI or RE or RME or RST or RSTI referring to at least one of the selected objects, then a conventional dialog box is displayed on the display device 106 to first alert the user about this situation and second to invite him to either cancel the deletion operation or to confirm it. If the user decision is to cancel the operation, then no action is taken, otherwise the selected objects are immediately deleted, so  
25 that they do no longer appear on the list boxes 213, 214 and 202. Alternatively the user can use the pointing device 105 to click on the "Edit" push-button 211 if he/she wants to edit the selected object which is assumed to be unique.

If no object or multiple objects have been previously selected, as shown within the RST Manager Dialog Box 200 by the presence of no or multiple check marks (visible  
30 or not) within the check boxes located on the left side, like the check box 212, then a warning message is displayed on the display device 106 to the user through similar conventional means such as pop-up windows, status bar messages, or any other spirit of the invention.

If a single object was previously selected, as shown by the presence of a single  
35 check mark (visible or not) within a check box located on the left side, like the check box 212, then the RST Manager Dialog Box 200 is first closed and afterwards the nature of this single selected object is taken into account to determine the new dialog box to be opened.

If the selected object was an EF or a MEF, then the **EF Editor** command is issued, so that the **EF Editor** method takes control by first displaying on the display device  
40 106 the EF Editor Dialog Box 301, as illustrated in FIG 3. The following steps of this scenario case are detailed in a subsequent section.

If the selected object was an EP or a MEP, then the **EP Editor** command is issued, so that the **EP Editor** method takes control by first displaying on the display device  
45 106 the EP Editor Dialog Box 401, as illustrated in FIG 4. The following steps of this scenario case are detailed in a subsequent section.

If the selected object was a RE or a RME, then the **RE Editor** command is issued, so that the **RE Editor** method takes control by first displaying on the display device  
50 106 the RE Editor Dialog Box 2321, as shown in FIG 20B. The following steps of this scenario case are detailed in a subsequent section.

If the selected object was a ST, then the **ST Editor** command is issued, so that the **ST Editor** method takes control by first displaying on the display device 106 the ST Editor Dialog Box 501, as illustrated in FIG 5. The following steps of this scenario case are detailed in a subsequent section.

If the selected object was a RST, then the **RST Editor** command is issued, so that the **RST Editor** method takes control by first displaying on the display device 106 the RST Editor Dialog Box 601, as illustrated in FIG 6. The following steps of this scenario case are detailed in a subsequent section.

Alternatively the user can use the pointing device 105 to click on the "*Instanciate*" push-button 204 if he/she wants to generate either a STI or a RSTI which abides by the selected object which is assumed to be unique and to be respectively a ST or a RST.

5 If no object or multiple objects have been previously selected, as shown within the RST Manager Dialog Box 200 by the presence of no or multiple check marks (visible or not) within the check boxes located on the left side, like the check box 212, then a warning message is displayed on the display device 106 to the user through conventional means such as pop-up windows, status bar messages, or any other similar conventional means which can be used instead without departing from the spirit of the invention.

10 If a single object was previously selected, as shown by the presence of a single check mark (visible or not) within a check box located on the left side, like the check box 212, then the method checks if this object is a ST or a RST.

15 If it is not the case, then a warning message is displayed on the display device 106 to the user through conventional means such as pop-up windows, status bar messages, or any other similar conventional means which can be used instead without departing from the spirit of the invention.

20 If a single ST (respectively RST) object was previously selected, then the RST Manager Dialog Box 200 is first closed and afterwards the *ST Instanciator* (resp. *RST Instanciator*) command is issued, so that the *ST Instanciator* (resp. *RST Instanciator*) method takes control by first displaying on the display device 106 the ST Instanciator Dialog Box 1300 (resp. RST Instanciator Dialog Box 2300), as shown in FIG 13A (resp. 20A). The following steps of this scenario case are detailed in subsequent sections.

25 Alternatively the user can use the pointing device 105 to click on the "*Export*" push-button 206 if he/she wants to export a non-empty set of objects from the current spreadsheet file to another spreadsheet file. If the check box "*Including child objects (for Export)*" 220 is filled with a check mark, then all the child objects of the selected objects will also benefit from the export operation, even if these child objects are not selected through the check boxes located on the left side, like the check box 212.

30 If no object has been previously selected, as shown within the RST Manager Dialog Box 200 by the absence of any check mark (visible or not) within the check boxes located on the left side, like the check box 212, then a warning message is displayed on the display device 106 to the user through conventional means such as pop-up windows, status bar messages, or any other similar conventional means which can be used instead without departing from the spirit of the invention.

35 If one or multiple objects were previously selected, as shown by the presence of at least one check mark (visible or not) within a check box located on the left side, like the check box 212, then the RST Manager Dialog Box 200 is first closed and afterwards a specific *RST Export Manager* command is issued, so that a dedicated method, not described in the present invention, takes control to handle the export operation.

40 Alternatively the user can use the pointing device 105 to click on the "*Import*" push-button 205 if he/she wants to import one or several objects from another spreadsheet file to the current spreadsheet file. The RST Manager Dialog Box 200 is first closed and afterwards a specific *RST Import Manager* command is issued, so that a dedicated method, not described in the present invention, takes control to handle the import operation.

45 Alternatively the user can use the pointing device 105 to click on one of the five option-buttons 217 "*Format*", 209 "*Profile*", 216 "*Template*", 218 "*RE*", 219 "*Recursive Template*", on the bottom left side of the RST Manager Dialog Box 200, if

he/she wants to specify which type of new object may be created afterwards. As five option-buttons are available on the RST Manager Dialog Box 200, the user has the choice to specify either a EF, or a EP or a RE or a ST or a RST as the type of the new object to be created afterwards.

Alternatively the user can use the pointing device 105 to click on the check-box 208 entitled "*From current selection*", if he/she wants to specify if the next object to be created afterwards will be derived or not from the range of cells currently selected in the spreadsheet file.

Alternatively the user can use the pointing device 105 to click on the "*Create New*" push-button 210 if he/she wants to create a new object whose type has been previously specified thanks to the three option-buttons like

- the "*Profile*" option-button 209, or
- the "*Format*" option-button 217, or
- the "*Template*" option-button 216, or
- The "*RE*" option-button 218, or
- The "*Recursive Template*" option-button 219.

If none of these five option-buttons shows a previous user choice, as shown within the RST Manager Dialog Box 200 by the absence of a point within one of these five option-buttons 209, 216, 217, 218 and 219, then a warning message is displayed on the display device 106 to the user through conventional means such as pop-up windows, status bar messages, or any other similar conventional means which can be used instead without departing from the spirit of the invention.

If one of these five option-buttons 209, 216, 217, 218 and 219 shows a previous user choice, then the RST Manager Dialog Box 200 is first closed and afterwards the single selected option-button is taken into account to determine the new dialog box to be opened.

If the "*Format*" option-button 217 shows a selection, then the **EF Editor** command is issued, so that the **EF Editor** method takes control by first displaying on the display device 106 the EF Editor Dialog Box 301, as shown in FIG 3. The following steps of this scenario case are detailed in a subsequent section.

If the "*Profile*" option-button 209 shows a selection, then the **EP Editor** command is issued, so that the **EP Editor** method takes control by first displaying on the display device 106 the EP Editor Dialog Box 401, as shown in FIG 4. The following steps of this scenario case are detailed in a subsequent section.

If the "*Template*" option-button 216 shows a selection, then the **ST Editor** command is issued, so that the **ST Editor** method takes control by first displaying on the display device 106 the ST Editor Dialog Box 501, as illustrated in FIG 5. The following steps of this scenario case are detailed in a subsequent section.

If the "*RE*" option-button 218 shows a selection, then the **RE Editor** command is issued, so that the **RE Editor** method takes control by first displaying on the display device 106 the RE Editor Dialog Box 2321, as illustrated in FIG 20B. The following steps of this scenario case are detailed in a subsequent section.

If the "*Recursive Template*" option-button 219 shows a selection, then the **RST Editor** command is issued, so that the **RST Editor** method takes control by first displaying on the display device 106 the RST Editor Dialog Box 601, as illustrated in FIG 6. The following steps of this scenario case are detailed in a subsequent section.

Finally the user can use the pointing device 105 to click on the "*Done*" push-button 201 or on the closing-window push-button 215 if he/she wants to quit the RST Manager method. The resulting effect is to close the RST Manager Dialog Box 200 on the display device 106.

- b. **EF Editor**: According to the previous scenario illustrating the **RST Manager** method, the spreadsheet user may then invoke an original specific command called



5 "EF Editor" thanks to conventional means available in spreadsheet environment, such as but not limited to the pointing device 105 or the keyboard 104, in order to either create a new EF; or to create a new MEF; or to update an existing EF; or to update an existing MEF. The corresponding scenario is described in international patent application PCT/EP 02/09483 (IBM's reference FR9 2001 0029) entitled "System and method in an electronic spreadsheet for exporting-importing the content of input cells from a scalable template instance to another" by Aureglia et al.

- 10 • c. EP Editor: According to the previous scenario illustrating the *RST Manager* method, the spreadsheet user may then invoke an original specific command called "EP Editor" thanks to conventional means available in spreadsheet environment, such as but not limited to the pointing device 105 or the keyboard 104, in order to either create a new EP or to create a new MEP or to update an existing EP or to update an existing MEP.

15 The corresponding scenario is described in international patent application PCT/EP 02/09483 (IBM's reference FR9 2001 0029) entitled "System and method in an electronic spreadsheet for exporting-importing the content of input cells from a scalable template instance to another" by Aureglia et al.

- 20 • d. RE Editor: According to the previous scenario illustrating the *RST Manager* method, the spreadsheet user may then invoke an original specific command called "RE Editor" thanks to conventional means available in spreadsheet environment, such as but not limited to the pointing device 105 or the keyboard 104, in order to either create a new RE or to create a new RME or to update an existing RE or to update an existing RME.

25 This can be illustrated with the user interface described with the FIG 20B, showing the RE Editor Dialog Box 2321, as displayed on the display device 106 within the GUI window of the electronic spreadsheet office application.

When the RE Editor Dialog Box 2321 is displayed on the display device 106, it contains some pieces of information.

30 First the nature of the edited object is shown by a pair of option-buttons 2330 and 2331 which specifies if it is either a RE or a RME. The spreadsheet user can click with the pointing device 105 on one of these two option-buttons 2330 and 2331 to swap between a RE definition and a RME definition.

35 Second the number of fields within the edited object is specified in the text-box 2326. When a new RE or RME is created (the spreadsheet user having previously clicked with the pointing device 105 on the option-button 218 to put a point on it and on the push-button 210, all contained within the RST Manager Dialog Box 200, as illustrated by FIG 2), the value shown by the text box 2326 corresponds to a default value set to 3 in a preferred embodiment of the present invention. When an existing RE or RME is edited, the value shown by the text box 2326 corresponds to the number of fields previously defined for this object. In all cases, the spreadsheet user can change the value shown in the text box 2326 by clicking with the pointing device 105 on the spin-button 2327, either on the ascending or on the descending side, so that the value can get increased or decreased (within predefined boundaries).

40 Third the name of the edited RE or RME is displayed on the label box 2324. When an existing RE or RME is edited, the name shown by the label box 2324 corresponds to the name previously assigned to this object. When a new RE or RME is created, then the name displayed on the label box 2324 corresponds to a default value which, in a preferred embodiment of the present invention, takes the form "New XX" where XX is a counter ensuring the uniqueness of the assigned name.

45 Fourth the ST's constituting the edited RE or RME are jointly specified by the text boxes 2335 and 2334. The text box 2335 specifies a field rank, which by convention takes the value 1 for the leftmost field of the edited RE or RME, and takes the same value as the one displayed in the text box 2326 for the rightmost field of the edited

50

RE or RME. The text box 2334 specifies the name of the ST for the field whose rank is specified by the text box 2335.

The RE Editor Dialog Box 2321 contains several graphical objects which allow the spreadsheet user to take some actions.

5 First the spreadsheet user can assign a new name to the currently edited RE or RME. For this purpose he/she will first use conventional means such as the keyboard 104 to specify within the text box 2325 the new name to be given to the edited RE or RME. Then he/she will use the pointing device 105 to click on the "Save As" push-button 2332. If the specified name entered within the text box 2325 was already assigned to an existing object or was not a valid name, then a warning message is displayed on the display device 106 to the user through conventional means such as pop-up windows, status bar messages, or any other similar conventional means which can be used instead without departing from the spirit of the invention. This warning message informs the spreadsheet user about this situation and then prompts him for acknowledgment. Then the text box 2325 is cleared without further action. If the specified name entered within the text box 2325 was not yet assigned to an existing object and was a valid name, then the text box 2325 is cleared and the edited object is saved on the spreadsheet file under the new name which is in turn displayed within the label box 2324.

20 Second the spreadsheet user can save on the spreadsheet file the current definition of the edited object by clicking with the pointing device 105 on the "Save" push-button 2333. This event results in checking if the updated RE or RME is already referenced by an existing RST. If it is not the case, then the updated definition of the RE or RME is saved on the spreadsheet file. If it is the case, then a warning message is displayed on the display device 106 to the user through conventional means such as pop-up windows, status bar messages, or any other similar conventional means which can be used instead without departing from the spirit of the invention. This warning message informs the spreadsheet user about this situation and then prompts him for either canceling the operation or for pursuing it. In the first case the updated RE or RME definition is not saved while it is saved on the spreadsheet file in the second case.

30 Third the spreadsheet user can change the definition of the ST's constituting the edited RE or RME. For this purpose he/she will first navigate within the fields of the edited object by clicking with the pointing device 105 on the spin-button 2329 to either decrement or increment the rank of the field, as displayed in the text box 2335, and whose ST name is displayed in the text box 2334. The value taken by the field rank is kept within an interval lower bounded by the value 1 (one) and upper bounded by the value of the text box 2326. Then the spreadsheet user can update the name of the ST for the field whose rank is displayed in the text box 2335 by clicking with the pointing device 105 on the spin-button 2328 to select an available ST name.

40 Finally the user can use the pointing device 105 to click on the "Done" push-button 2323 or on the closing-window push-button 2322 if he/she wants to quit the RE Editor method. The resulting effect is to close the RE Editor Dialog Box 2321 on the display device 106.

45 • **e. ST Editor:** According to the previous scenario illustrating the *RST Manager* method, the spreadsheet user may then invoke an original specific command called "**ST Editor**" thanks to conventional means available in spreadsheet environment, such as but not limited to the pointing device 105 or the keyboard 104, in order to either create a new ST or to update an existing ST. The corresponding scenario is described in international patent application PCT/EP 02/09483 (IBM's reference FR9 2001 0029) entitled "System and method in an electronic spreadsheet for

50



exporting-importing the content of input cells from a scalable template instance to another" by Aureglia et al.

- 5     **f. RST Editor:** According to the previous scenario illustrating the *RST Manager* method, the spreadsheet user may then invoke an original specific command called  
 10     **"RST Editor"** thanks to conventional means available in spreadsheet environment, such as but not limited to the pointing device **105** or the keyboard **104**, in order to either create a new RST or to update an existing RST. This can be illustrated with the user interface described with the FIG 6, showing the RST Editor Dialog Box **601**, as displayed on the display device **106** within the GUI window **611** of the electronic spreadsheet office application. When the RST Editor Dialog Box **601** is displayed on the display device **106**, the current sheet becomes a dedicated sheet entitled "*Editor Space*" **615** in a preferred embodiment of the present invention. Within the "*Editor Space*" **615** sheet, the RST to be edited appears as a range of cells **614** in the top left angle, with the top left cell at address B2. Although the edited RST corresponds to a regular range of cells **614** within a sheet, conventional tools available in electronic spreadsheet environments cannot be used to update this range of cells **614**. The spreadsheet user will only be able to navigate within the range of cells **614** illustrating the RST, and to either insert or delete rows within the range of cells **614** illustrating the RST, by using dedicated means which are part of the RST Editor Dialog Box **601**. Row insertion or deletion in the "*Editor Space*" sheet **615** will be disabled. Moreover the "*Editor Space*" sheet **615** is write-protected to prevent the user to inadvertently modify the settings of the RE's or RME's defined as part of the RST illustrated by the range of cells **614**. When the RST Editor Dialog Box **601** is displayed on the display device **106**, it contains some pieces of information which either relate to the whole RST, as illustrated by the range of cells **614**, or which relate to the RE or RME pointed by the cell currently selected within this same range of cells **614**.

First the RE or RME pointed by the cell currently selected is shown by the "*RE*" combo box **610**. By clicking with the pointing device **105** on the arrow located on the right side of this "*RE*" combo box **610**, the spreadsheet user can display and navigate within the list of defined RE's and RME's, then select a RE or RME of his/her choice and his/her choice appearing on the row where is located the currently selected cell within the range of cells **614**. If the spreadsheet user changes the selected row within the range of cells **614**, by clicking with the pointing device **105** on the "*Up*" push-button **619**, or on the "*Down*" push-button **616**, then the name displayed within the combo box **610** is updated to specify the name of the RE or RME corresponding to the new selected row. If the spreadsheet user wishes to insert a new RME either in the header or in the footer part of the RST, he/she has just to click with the pointing device **105** on the "*Add*" push-button **617** to insert a new row within the range of cells **614**, at the desired place above the last position of the currently selected cell. Then the range of cells **614** is updated with a new row being displayed on the window **611**. Then the RST Editor Dialog Box **601** is updated by showing within the combo boxes **610** the name assigned by default to the introduced RME. If the spreadsheet user wishes to remove a RME either from the header part or from the footer part of the RST, he/she has just to click with the pointing device **105** on the "*Delete*" push-button **618** to remove the corresponding row within the range of cells **614**, at the desired place. Then the currently selected cell within the range of cells **614** becomes the one belonging to the row representing the unique RE defined within the RST, and the RST Editor Dialog Box **601** is updated by showing within the combo box **610** the name of the unique RE defined within the RST.

Second the minimum number of RE's allowed within a RSTI abiding by the edited RST is specified in the "*MIN*" text-box **606**. Similarly the maximum number of RE's

5 allowed within a RSTI abiding by the edited RST is specified in the "MAX" text-box 609. When a new RST is created (the spreadsheet user having previously clicked with the pointing device 105 on the option-button 219 to put a point on it and on the push-button 210, all contained within the RST Manager Dialog Box 200, as illustrated by FIG. 2), the value shown by the "MIN" text-box 606 corresponds to a default value set to 1 in a preferred embodiment of the present invention, and the value shown by the "MAX" text box 609 corresponds to a default value set to 16 in a preferred embodiment of the present invention. When an existing RST is edited, the values shown by the text boxes 606 and 609 correspond respectively to the minimum and maximum number of RE's allowed in any RSTI abiding by the currently edited RST, as previously defined by the spreadsheet user. In all cases, the spreadsheet user can change the values shown in the text box "MIN" 606 or in the text box "MAX" 609 by clicking with the pointing device 105 respectively on the spin-button 607 or on the spin-button 608, either on the ascending or on the descending side, so that the values can get increased or decreased (within predefined boundaries), while ensuring that the value specified in the "MIN" text box 606 remains less than or equal to the value specified in the "MAX" text box 609. Should any existing RSTI abiding by the updated RST have a number of elements falling outside the new "MIN"- "MAX" interval, then this RSTI will not be impacted by the RST update, but any future addition or removal of RE's will be done according to the new definition of the "MIN"- "MAX" interval.

10 Third the name of the edited RST is displayed on the label box 604. When an existing RST is edited, the name shown by the label box 604 corresponds to the name previously assigned to this object. When a new RST is created, then the name displayed on the label box 604 corresponds to a default value which, in a preferred embodiment of the present invention, takes the form "New XX" where XX is a counter ensuring the uniqueness of the assigned name.

15 The RST Editor Dialog Box 601 comprises several graphical objects which allow the spreadsheet user to take some actions.

20 First the spreadsheet user can assign a new name to the currently edited RST, if this RST is currently constituted by RE's and RME's having all the same number of fields. Indeed in this case the "Save As" push-button 612 is enabled, so that any click on it with the pointing device 105 is recognized as a valid event. The spreadsheet user will first use conventional means such as the keyboard 104 to specify within the text box 605 the new name to be given to the edited RST. Then he/she will use the pointing device 105 to click on the "Save As" push-button 612. If the specified name entered within the text box 605 was already assigned to an existing object or is not a valid name, then a warning message is displayed on the display device 106 to the user through conventional means such as pop-up windows, status bar messages, or any other similar conventional means which can be used instead without departing from the spirit of the invention. This warning message informs the spreadsheet user about this situation and then prompts her/him for acknowledgment. Then the text box 605 is cleared without further action. If the specified name entered within the text box 605 was not yet assigned to an existing object and is a valid name, then the text box 605 is cleared and the edited RST is saved on the spreadsheet file under the new name which is in turn displayed within the label box 604.

25 The spreadsheet user can save on the spreadsheet file the current definition of the edited RST, if this RST is currently constituted by RE's and RME's having all the same number of fields. Indeed in this case the "Save" push-button 613 is enabled, so that any click on it with the pointing device 105 is recognized as a valid event. This event results in checking if the updated RST is already referenced by an existing RSTI. If it is not the case, then the updated definition of the RST is saved on the spreadsheet file. If it is the case, then a warning message is displayed on the

display device 106 to the user through conventional means such as pop-up windows, status bar messages, or any other similar conventional means which can be used instead without departing from the spirit of the invention. This warning message informs the spreadsheet user about this situation and then prompts him for either canceling the operation or for pursuing it. In the first case the updated RST definition is not saved while it is saved on the spreadsheet file in the second case.

Finally the user can use the pointing device 105 to click on the "Done" push-button 603 or on the closing-window push-button 602 if he/she wants to quit the RST Editor method. The resulting effect is to close the RST Editor Dialog Box 601 on the display device 106 and to revert to the sheet which was active when the **RST Editor** command was first invoked.

- **g. ST Instanciator** : According to the previous scenario illustrating the **RST Manager** method, the spreadsheet user may then invoke an original specific command called "**ST Instanciator**" thanks to conventional means available in spreadsheet environment, such as but not limited to the pointing device 105 or the keyboard 104, in order to create a STI abiding by a selected ST and located according to the currently selected cell. The corresponding scenario is described in international patent application PCT/EP 02/09483 (IBM's reference FR9 2001 0029) entitled "System and method in an electronic spreadsheet for exporting-importing the content of input cells from a scalable template instance to another" by Aureglia et al.
- **h. RST Instanciator**: According to the previous scenario illustrating the **RST Manager** method, the spreadsheet user may then invoke an original specific command called "**RST Instanciator**" thanks to conventional means available in spreadsheet environment, such as but not limited to the pointing device 105 or the keyboard 104, in order to create a RSTI abiding by a selected RST and located according to the currently selected cell. This can be illustrated with the user interface described with the FIG 20A, showing the RST Instanciator Dialog Box 2300, as displayed on the display device 106. When the RST Instanciator Dialog Box 2300 is displayed on the display device 106, the current sheet remains still active, so that the spreadsheet user can visualise the data present on it. The RST Instanciator Dialog Box 2300 contains some pieces of information which relate to the instantiation operation.

First the name of the RST that abides by the RSTI to be created, is displayed in a label box 2302.

Second the number of RE's to be present at RSTI creation time is shown in a text box 2311. This number takes a default value equal to the minimum number of RE's, as specified in the definition of the RST that abides by the RSTI to be created. If the spreadsheet user wished to create a RSTI with another number of RE's, then he/she will have to click with the pointing device 105 on the upper or lower side of the spin-button 2303 to either increase or decrease the number of RE's. This number of RE's will vary within a range delimited by the minimum and maximum number of RE's, as specified within the definition of the RST (fields "Min Element #" 2225 and "Max Element #" 2226 within a record 2221 of the RSTT table 2220 whose "Name" field 2222 matches the name displayed in the label box 2302) and is displayed, after possible update, in the text box 2311.

Third the push-button "Cancel" 2308 or the closing-window push-button 2301 allow to close the RST Instanciator Dialog Box 2300 without further action. By clicking with the pointing device 105 on one of these two push-buttons 2301 and 2308, the RST Instanciator Dialog Box 2300 is closed and the RST instantiation operation is aborted.

Fourth the push-button "Create Instance" 2310, when first enabled and second clicked with the pointing device 105 by the spreadsheet user, is the trigger launching the operation of RST instantiation. This push-button "Create Instance" 2310 is

enabled (meaning that the method recognises the click event with the pointing device 105 on this push-button "Create Instance" 2310) when the instantiation operation is possible. The fact that this RST instantiation is possible or not depends on different factors: the position of the currently selected cell within the current sheet of the electronic spreadsheet, the size of the RSTI to be created, the presence of any existing STI belonging to the same sheet as the currently selected cell. The possibility to create or not a new RSTI with the size specified in the text box 2303, abiding by a RST whose name is specified by the label box 2302, with the top left corner located on the currently selected cell, is reflected by several label boxes, taking the values "YES" or "NO", which are part of the RST Instantiation Dialog Box 2300: the label box 2304 which reflects if the new RSTI is or not too wide, the label box 2305 which reflects if the new RSTI is or not too high, the label box 2306 which reflects if any existing STI is already defined on the sheet comprising the currently selected cell, and the label box 2307 which reflects if the creation of the new RSTI may lead to loose any existing data present in one or several spreadsheet cells. As soon as the value "YES" is taken by the label box 2304, or by the label box 2305, or by the label box 2306, then the RSTI creation is considered as impossible, so that the "Create Instance" push-button 2310 get disabled. If the value "no" is displayed in these three label boxes, then the instantiation operation is possible, so that the "Create Instance" push-button 2310 get enabled. When clicked with the pointing device 105 by the spreadsheet user, the instantiation operation is performed, and then the RST Instantiation Dialog Box 2300 is closed.

Fifth the push-button "Create instance in a new sheet" 2309, when first enabled and second clicked with the pointing device 105 by the spreadsheet user, is an alternative trigger launching the operation of RST instantiation, but in a sheet which is created as part of this instantiation operation. In a preferred embodiment of the present invention, the new sheet is created after the sheet comprising the currently selected cell. Any other sheet position could be used instead, without departing from the spirit of the current invention. This push-button "Create instance in a new sheet" 2309 is enabled (meaning that the method recognizes the click event with the pointing device 105 on this push-button "Create instance in a new sheet" 2309) when the instantiation operation is possible in a new sheet. The fact that this RST instantiation is possible or not in a new sheet depends on the size of the RSTI to be created. The possibility to create or not a new RSTI in a new sheet with the size specified in the text box 2303, abiding by a RST whose name is specified by the label box 2302, is reflected by several label boxes, taking the values "YES" or "NO", which are part of the RST Instantiation Dialog Box 2300: the label box 2304 which reflects if the new RSTI is or not too wide, and the label box 2305 which reflects if the new RSTI is or not too high. As soon as the value "YES" is taken by the label box 2304, or by the label box 2305, then the RSTI creation is considered as impossible in a new sheet, so that the "Create instance in a new sheet" push-button 2309 get disabled. If the value "no" is displayed in these two label boxes, then the instantiation operation is possible in a new sheet, so that the "Create instance in a new sheet" push-button 2309 get enabled. When clicked with the pointing device 105 by the spreadsheet user, the instantiation operation is performed in a new sheet, and then the RST Instantiation Dialog Box 2300 is closed.

## • 2. Second Operation : Removal of Elements from a Defined STI

The fourth operation occurs when the spreadsheet user decides, based on his or her own criteria not detailed here, either to remove some elements from a defined STI, or to clear the content of some elements within a defined STI, or to delete a whole defined STI, or even to delete some spreadsheet cells or columns or rows from the current sheet. The corresponding scenario is described in international patent application PCT/EP 02/09483 (IBM's reference FR9 2001 0029) entitled "System and method in an

electronic spreadsheet for exporting-importing the content of input cells from a scalable template instance to another" by Aureglia et al.

• **3. Third Operation: Removal of Elements from a Defined RSTI**

The fifth operation occurs when the spreadsheet user decides, based on his or her own criteria not detailed here, either to delete a whole defined RSTI, or to remove some RE's from a defined RSTI, or to delete selected elements within a STI comprised within a RSTI, or to clear the content of all elements within a selected STI comprised within a RSTI, or to clear the content of selected elements within a STI comprised within a RSTI, or to clear the content of selected elements comprised within the currently selected range of cells, or even to delete some spreadsheet cells or columns or rows from the current sheet.

In a preferred embodiment of the present invention, this operation comprises the following steps:

- **a.** The spreadsheet user first selects a range of cells of his/her choice by using conventional means, such as but not limited to the pointing device **105** or the keyboard **104**.

- **b. RSTI Deletion Manager**

Then the spreadsheet user invokes thanks to conventional means available in spreadsheet environment, such as (but not limited to)

- dedicated push-buttons,
- keyboard entry short cuts,
- menu or sub-menu entries,

an original specific command called "**RSTI Deletion Manager**" which enriches the conventional means for deleting cells or rows or columns within a spreadsheet. In a preferred embodiment of the present invention, the "**RSTI Deletion Manager**" command is invoked by using the same set of means as the one available in conventional electronic spreadsheets for clearing the content of a single cell or of a range of cells or for removing cells or rows or columns within a sheet, such as but not limited to

- keying the "Delete" key on the keyboard **104**, or
- clicking with the pointing device **105** on a "Delete" sub-menu entry of the "Range" menu entry, or
- keying the "Ctrl -" key on the keyboard **104**.

When the command is invoked, a test is first performed to determine if the currently selected cell belongs or not to a sheet which comprises a defined RSTI.

If it is not the case, then the command passes control to the **STI Deletion Manager** command, in order to take care of the presence of any STI that may be impacted by the deletion operation.

If it is the case, then a second test is performed to determine if the currently selected cell is comprised within the RSTI present on the current sheet.

If it is not the case, then the conventional deletion procedures available in the electronic spreadsheet environment are invoked, after having disabled any deletion mode which would corrupt the RSTI present on the current sheet. For instance, if the currently selected cell belongs to a row (respectively column) which is occupied by the RSTI present on the current sheet, then the row (respectively column) deletion mode is disabled.

If it is the case, then the deletion operation continues by displaying on the display device **106** the RSTI Deletion Manager Dialog Box **1940**, as illustrated by FIG **16C**, which contains some pieces of information which relate to the deletion operation. In the following, the RSTI contained on the same sheet as the currently selected cell will be referred to as the current RSTI or cRSTI for short.

First the name of the RST that the cRSTI abides by, is displayed in a label box **1950**. Second the different available modes of the deletion are specified through a set of option buttons:

- 5       • The option button "*delete IN fields in selected range*" 1949 allows, when enabled, to clear the content of the IN fields comprised within the currently selected range of cells. This option button "*delete IN fields in selected range*" 1949 is enabled if and only if the currently selected range of cells is comprised within the boundaries of a STI defined as part of the cRSTI. By referring to FIG 17A which illustrates a possible cRSTI structure, the option button "*delete IN fields in selected range*" 1949 is enabled when the currently selected range of cells corresponds to the ranges of cells 2018, or 2019, or 2020, or 2021, and is disabled when the currently selected range of cells corresponds to the ranges of cells 2022, or 2023, or 2024, or 2025.
- 10       • The option button "*delete IN fields in selected elements of current STI*" 1948 allows, when enabled, to clear the content of the IN fields comprised within the currently selected elements of the STI to which the currently selected cells belongs. This option button "*delete IN fields in selected elements of current STI*" 1948 is enabled if and only if the currently selected range of cells is comprised within the boundaries of a STI defined as part of the cRSTI. By referring to FIG 17A which illustrates a possible cRSTI structure, the option button "*delete IN fields in selected elements of current STI*" 1948 is enabled when the currently selected range of cells corresponds to the ranges of cells 2018, or 2019, or 2020, or 2021, and is disabled when the currently selected range of cells corresponds to the ranges of cells 2022, or 2023, or 2024, or 2025.
- 15       • The option button "*delete IN fields in current STI*" 1947 allows, when enabled, to clear the content of all the IN fields comprised within the STI to which the currently selected cells belongs. This option button "*delete IN fields in current STI*" 1947 is enabled if and only if the currently selected cell is comprised within the boundaries of a STI defined as part of the cRSTI. By referring to FIG 17A which illustrates a possible cRSTI structure, the option button "*delete IN fields in current STI*" 1947 is enabled when the currently selected cell corresponds to the ranges of cells 2018, or 2019, or 2020, or 2021, or 2023, or 2025, and is disabled when the currently selected cell corresponds to the ranges of cells 2022, or 2024.
- 20       • The option button "*delete selected elements in current STI*" 1946 allows, when enabled, to delete the selected elements of the STI to which the currently selected range of cells belongs. This option button "*delete selected elements in current STI*" 1946 is enabled if and only if the currently selected range of cells is comprised within the body part of a STI defined as part of the cRSTI. By referring to FIG 17A which illustrates a possible cRSTI structure, the option button "*delete selected elements in current STI*" 1946 is enabled when the currently selected range of cells corresponds to the ranges of cells 2018, or 2019, and is disabled when the currently selected range of cells corresponds to the range of cells 2020, or 2021, or 2022, or 2023, or 2024, or 2025.
- 25       • The option button "*delete STI(s) in current container*" 1945 allows, when enabled, to delete the one or plurality of STI(s) belonging to the container row to which the currently selected cells belongs. This option button "*delete STI(s) in current container*" 1945 is enabled if and only if the currently selected cell is comprised within the body part of cRSTI. By referring to FIG 17A which illustrates a possible cRSTI structure, the option button "*delete STI(s) in current container*" 1945 is enabled when the currently selected cell corresponds to the ranges of cells 2018, or 2019, or 2022, or 2023, and is disabled when the currently selected cell corresponds to the ranges of cells 2020, or 2021, or 2024, or 2025.
- 30       • The option button "*delete RSTI (preserving comprised STI's)*" 1944 allows to dequalify the range of cells cRSTI so that it becomes a set of STI's, but no longer treated as a RSTI. This option button "*delete RSTI (preserving comprised STI's)*"



**1944** is always enabled, and is the default deletion mode when the RSTI Deletion Manager Dialog Box **1940** is first displayed.

If the spreadsheet user wishes to change the default mode of deletion which is *"delete RSTI (preserving comprised STI's)"* **1944** or a previously changed mode of deletion, then he/she uses the pointing device **105** to click on one of the six option buttons, if enabled:

- *"delete RSTI (preserving comprised STI's)"* **1944**, or
- *"delete STI(s) in current container"* **1945**, or
- *"delete selected elements in current STP"* **1946**, or
- *"delete IN fields in current STP"* **1947**, or
- *"delete IN fields in selected elements of current STP"* **1948**, or
- *"delete IN fields in selected range"* **1949**,

which will display alone a black point specifying the new selected mode of deletion. Any attempt to click with the pointing device **105** on a disabled option button will have no effect.

Third the push-button *"Cancel"* **1943** or the closing-window push-button **1941** allow to close the RST Deletion Manager Dialog Box **1940** without further action. By clicking with the pointing device **105** on one of these two push-buttons **1941** and **1942**, the RST Deletion Manager Dialog Box **1940** is closed and the RSTI deletion operation is aborted.

Fourth the push-button *"Delete"* **1942**, when clicked with the pointing device **105** by the spreadsheet user, is the trigger launching the operation of RSTI deletion. This push-button *"Delete"* **1942** is always enabled (meaning that the method recognises the click event with the pointing device on this push-button *"Delete"* **1942**) as the deletion operation is always possible (at least with the default mode corresponding to the option button *"delete RSTI (preserving comprised STI's)"* **1944**). The deletion operation is performed according to the deletion mode selected by the spreadsheet user. This can be illustrated with the diagram of FIG **17A** where the cRSTI corresponds to the range of cells **2001**.

- If the deletion mode corresponds to the option button *"delete RSTI (preserving comprised STI's)"* **1944**, and the currently selected range of cells corresponds to the range of cells **2024**, then the deletion operation consists in dequalifying the range of cells **2001** as a RSTI. Nevertheless the collection of STI's which were forming the cRSTI are still qualified as STI's and can thus benefit from the associated tools.
- If the deletion mode corresponds to the option button *"delete STI(s) in current container"* **1945**, and the currently selected range of cells corresponds to the range of cells **2022**, then the deletion operation consists in removing from the cRSTI the row container **2010**, so that the cRSTI will contain afterwards only 2 RE's mapped to the container rows **2009** and **2008** (while the RME's **2012**, **2011**, and **2007** are untouched).
- If the deletion mode corresponds to the option button *"delete selected elements in current STP"* **1946**, and the currently selected range of cells corresponds to the range of cells **2019**, then the deletion operation consists in removing from the STI **2032** the elements occupying the same rows as the currently selected range of cells **2019**.
- If the deletion mode corresponds to the option button *"delete IN fields in current STP"* **1947**, and the currently selected range of cells corresponds to the range of cells **2021**, then the deletion operation consists in clearing all the IN fields belonging to the STI **2031**.
- If the deletion mode corresponds to the option button *"delete IN fields in selected elements of current STP"* **1948**, and the currently selected range of cells corresponds to the range of cells **2018**, then the deletion operation consists in

clearing all the IN fields belonging to the elements of the STI 2034 occupying the same rows as the currently selected range of cells 2018.

- If the deletion mode corresponds to the option button "delete IN fields in selected range" 1949, and the currently selected range of cells corresponds to the range of cells 2020, then the deletion operation consists in clearing the IN fields of the STI 2030 belonging to the currently selected range of cells 2020.

Once the deletion operation is complete, the RSTI Deletion Manager Dialog Box 1940 is closed, ending the command "RSTI Deletion Manager".

## E.METHODS

### 10 E1. RST Manager method

The method for managing EF's, MEF's, EP's, MEP's, ST's, RE's and RST's used in the preferred embodiment of the present invention is summarized in flowchart 800 of FIG 8. This method can be seen as the processing of the **RST Manager** command.

- At step 801, the method is in its default state, waiting for an event to initiate the process.

- At step 802, the **RST Manager** command is detected, as a result of a user action. This action can be for instance:

- a specific combination of key on the keyboard 104, or
- the click of the pointing device 105 on a specific button, or
- any other similar means not further specified here.

- At step 803, some local variables are initialized:

- the local variable *RSTM\_select* is set to the value 0 (zero),
- the local variable *RSTM\_new* is set to the value "NONE",
- the local variable *RSTM\_range* is set to the value "NO", and
- the local variable *RSTM\_index* is set to the value 1 (one), and
- The local variable *RSTM\_child* is set to the value "NO".

- At step 804, the five tables EFT 700, EPT 710, STT 720, RET 2210 and RSTT 2220 are parsed to derive the table RSTMT 2230. For each respective record 701, or 711, or 721, or 2211, or 2221 found in one of these five tables, is created a new record 2231 within the RSTMT table 2230.

Referring now to FIG 7A, 7B, 7C, 19A, 19B and 19C, this construction is done by copying in sequence all the fields defined in the record 701 ("Name" field 702, "Last Change Date" field 703, "Description Ptr" field 704, "Row #" field 705, "Column #" field 706 and "Type" field 707), or in the record 711 ("Name" field 712, "Last Change Date" field 713, "Description Ptr" field 714, "Row #" field 715, "Column #" field 716 and "Type" field 717), or in the record 721 ("Name" field 722, "Last Change Date" field 723, "Description Ptr" field 724, "Min Element #" field 725, "Max Element #" field 726 and "Type" field 727), or in the record 2211 ("Name" field 2212, "Last Change Date" field 2213, "Description Ptr" field 2214, "Row #" field 2215, "Column #" field 2216 and "Type" field 2217), or in the record 2221 ("Name" field 2222, "Last Change Date" field 2223, "Description Ptr" field 2224, "Min Element #" field 2225, "Max Element #" field 2226 and "Type" field 2227) onto the corresponding fields of the record 2231 ("Name" field 2232, "Last Change Date" field 2233, "Description Ptr" field 2234, "Info Field 1" field 2235, "Info Field 2" field 2236 and "Type" field 2237), then by initializing in the "Type" field 2237 the "SELECTED" attribute 2242 to "NO" and the "NATURE" attribute 2241 to the values "FORMAT", or "PROFILE" or "TEMPLATE" or "RECELEMENT" or "RECTEMPLATE" if the record 2231 has been respectively copied from a record 701, or 711, or 721, or 2211, or 2221 and then by initializing the last field "Index" 2238 with the value of a counter which increments for each new record and which starts with the value 1 (one).

- At step 805, the RST Manager Dialog Box 200 is displayed on the display device 106.
  - The "Name" information appearing on the top of the list box 213 corresponds to the "Name" field 2232 of the record 2231 in the RSTMT table 2230 whose "Index" field 2238 is equal to the local variable *RSTM\_index*. Underneath "Name" information's



within this list box 213 correspond to the "Name" field 2232 of the following records 2231 of the RSTMT table 2230.

- The "Type" information appearing on the top of the list box 214 is derived from the "Type" field 2237 (attributes "NATURE" 2241 and "META" 2239) of the record 2231 in the RSTMT table 2230 whose "Index" field 2238 is equal to the local variable *RSTM\_index*. Underneath "Type" information's within this list box 213 are derived from the "Type" field 2237 (attributes "NATURE" 2241 and "META" 2239) of the following records 2231 of the RSTMT table 2230.
- The "Modified" information appearing on the top of the list box 202 corresponds to the "Last Change Date" field 2233 of the record 2231 in the RSTMT table 2230 whose "Index" field 2238 is equal to the local variable *RSTM\_index*. Underneath "Modified" information's within this list box 213 correspond to the "Last Change Date" field 2233 of the following records 2231 of the RSTMT table 2230.
- The check box 212 is filled with a check mark if the "Type" field 2237 of the record 2231 in the RSTMT table 2230 whose "Index" field 2238 is equal to the local variable *RSTM\_index* has the "SELECTED" attribute 2242 equal to "YES". Underneath check boxes on the left of the list box 213 are also derived from the "Type" field 2237 ("SELECTED" attribute 2242) of the following records 2231 of the RSTMT table 2230.
- The option button "Format" 217 displays a black point if and only if the local variable *RSTM\_new* is equal to "FORMAT". The option button "Profile" 209 displays a black point if and only if the local variable *RSTM\_new* is equal to "PROFILE". The option button "Template" 216 displays a black point if and only if the local variable *RSTM\_new* is equal to "TEMPLATE". The option button "RE" 218 displays a black point if and only if the local variable *RSTM\_new* is equal to "RECELEMENT". The option button "Recursive Template" 219 displays a black point if and only if the local variable *RSTM\_new* is equal to "RECTEMPLATE".
- The check box "From current selection" 208 displays a check mark if and only if the local variable *RSTM\_range* is equal to "YES".
- The check box "Including child objects (for Export)" 220 displays a check mark if and only if the local variable *RSTM\_child* is equal to "YES".
- At step 806, the method is waiting for any user action on the RST Manager Dialog Box 200. Such user action is typically resulting from a click with the pointing device 105, but take other similar forms such as, but not limited to a specific combination of key on the keyboard 104, or any other similar means not further specified here.
- At step 807, a user action on the RST Manager Dialog Box 200 is detected.
  - If the user action is a click on the push-button "Delete" 207, then control is given to step 808;
  - if the user action is a click on the push-button "Import" 205, then control is given to step 810;
  - if the user action is a click on the push-button "Done" 201 or on the closing-window push-button 215, then control is given to step 834;
  - if the user action is a click on the push-button "Export" 206, then control is given to step 811;
  - if the user action is a click on the scrolling bar 203, either on the up direction or on the down direction, then control is given to step 814;
  - if the user action is a click on the option buttons "Format" 217, or "Profile" 209, or "Template" 216, or "RE" 218, or "Recursive Template" 219, then control is given to step 815;
  - if the user action is a click on the check box "From current selection" 208, then control is given to step 816;
  - if the user action is a click on the check box "Including child objects (for Export)" 220, then control is given to step 841;

- if the user action is a click on a top check box like the check box 212, then control is given to step 817;
- if the user action is a click on the push-button "Instanciate" 204, then control is given to step 830;
- 5 ~~• if the user action is a click on the push-button "Edit" 211, then control is given to step 824 and;~~
- if the user action is a click on the push-button "Create New" 210, then control is given to step 818.
- 10 • At step 808, a test is performed on each of the records 2231 of the RSTMT table 2230 whose "Type" field 2237 has the "SELECTED" attribute 2242 with the subfield "REFERENCED OBJECT" (RO) 2240d equal to "YES" or with the subfield "INSTANCE REFERENCE" (IR) 2240c larger than 1 (one) (this test determines if there exist some objects referring to one of the selected objects, or if there exist some instance abiding by one of the selected objects).
- 15 • If it is the case, then control is given to step 835 (meaning that at least one record 2231 of the RSTMT table 2230 previously selected was referenced by a ST, or by a STI, or by a RE, or by a RST, or by a RSTI);
- otherwise control is given to step 809.
- 20 • At step 809, each respective record 701, 711, 721, 2211 and 2221 is removed from the EFT table 700, EPT table 710, STT table 720, RET table 2210, and RSTT table 2220, if the corresponding respective "Name" field 702, 712, 722, 2212, and 2222 matches the "Name" field 2232 of a record 2231 of the RSTMT table 2230 whose "Type" field 2237 has the "SELECTED" attribute 2242 equal to "YES", as resulting from the step 817. Then the local variable *RSTM\_select* is reset to the value 0 (zero). Then control is given to the
- 25 step 804 for rebuilding the RSTMT table 2230.
- At step 810, the *RST Import Manager* command is issued and then control is given to step 834.
- At step 811, a test is performed to determine if the local variable *RSTM\_select* is equal to 0 (zero).
- 30 • If it is the case, then control is given to step 813;
- otherwise control is given to step 812.
- At step 812, the *RST Export Manager* command is issued and then control is given to step 834.
- 35 • At step 813, a warning message notification is issued for informing the user that at least one object must be selected prior clicking on the "Export" push-button 206. This can typically be done by displaying on the display device 106 a warning message in a pop-up window, or in a status bar area, but any other similar means could be used instead, without departing from the spirit of the invention. Once the user has acknowledged this notification message through conventional means such as clicking with the pointing
- 40 device 105 on an "OK" push-button present within a warning message pop-up window, or any other similar means without departing from the spirit of the invention, control is given to step 805.
- At step 814, the local variable *RSTM\_index* is either incremented or decremented by 1 (one) according to the direction (up or down) specified by the pointing device 105 on the scrolling bar 203, and as long as its value remains positive and less than or equal to the number of records 2231 defined within the RSTMT table 2230. Then control is given to
- 45 step 805.
- At step 815, the local variable *RSTM\_new* is updated to reflect the option button hit by the user with the pointing device 105.
- 50 • If the user has clicked on the "Format" option button 217, then the local variable *RSTM\_new* takes the value "FORMAT".
- If the user has clicked on the "Profile" option button 209, then the local variable *RSTM\_new* takes the value "PROFILE".

- If the user has clicked on the "Template" option button 216, then the local variable *RSTM\_new* takes the value "TEMPLATE".
- If the user has clicked on the "RE" option button 218, then the local variable *RSTM\_new* takes the value "RECELEMENT".
- If the user has clicked on the "Recursive Template" option button 219, then the local variable *RSTM\_new* takes the value "RECTEMPLATE".

Then control is given to step 805.

- At step 816, the local variable *RSTM\_range* is updated, so that its value swaps between "yes" and "no". In addition, a check mark is respectively added within or removed from the check box 206 if it was previously absent or present in this same check box 206. Then control is given to step 805.

- At step 817, the method updates the value of the "Type" field 2237 of the record 2231 within the RSTMT table 2230, whose "Name" field 2232 is found equal to the character string located within the list box 213 immediately on the right of the check box on which the user has just clicked.

If the previous value of this "Type" field 2237 had the "SELECTED" attribute 2242 equal to "yes", then the value update consists in turning this "SELECTED" attribute 2242 to "no" ; reversibly if the previous value of the "SELECTED" attribute 2242 was equal to "no", then the value update consists in turning this "SELECTED" attribute 2242 to "yes".

In the first case the local variable *RSTM\_select* is decremented by 1, and in the second case the local variable *RSTM\_select* is incremented by 1.

Furthermore in the first case the check mark previously present in the check box on which the user has just clicked is removed from this check box and in the second case a check mark is displayed in the check box on which the user has just clicked. Then control is given to step 805.

- At step 818, a test is performed to determine if the local variable *RSTM\_new* is equal to "NONE". If it is the case, then control is given to step 819; otherwise control is given to step 820.

- At step 819, a warning message notification is issued for informing the user that at least one option ("Format" option button 217, or "Profile" option button 209, or "Template" option button 216, or "RE" option button 218, or "Recursive Template" option button 219) must be selected prior clicking on the "Create New" push-button 210. This can typically be done by displaying on the display device 106 a warning message in a pop-up window, or in a status bar area, but any other similar means could be used instead, without departing from the spirit of the invention. Once the user has acknowledged this notification message through conventional means such as clicking with the pointing device 105 on an "OK" push-button present within a warning message pop-up window, or any other similar means without departing from the spirit of the invention, control is given to step 805.

- At step 820, a test is performed to determine the value taken by the local variable *RSTM\_new*.

- If found equal to "FORMAT", then control is given to step 821;
- If found equal to "PROFILE", then control is given to step 822;
- If found equal to "TEMPLATE", then control is given to step 823.
- If found equal to "RECELEMENT", then control is given to step 836.
- If found equal to "RECTEMPLATE", then control is given to step 837.

- At step 821, the **EF Editor** command is issued with passing two parameters ("NEW" ; *RSTM\_range*) and then control is given to step 834.

- At step 822, the **EP Editor** command is issued with passing two parameters ("NEW" ; *RSTM\_range*) and then control is given to step 834.

- At step 823, the **ST Editor** command is issued with passing one parameter ("NEW") and then control is given to step 834.

- At step 824, a test is performed to determine if the local variable *RSTM\_select* is equal to 1 (one). If it is the case, then control is given to step 825; otherwise control is given to step 829.
- 5 ~~• At step 825, a test is performed to determine the nature of the selected object, as specified by the "Type" field 2237 "NATURE" attribute 2241 of the corresponding record 2231 of the RSTMT table 2230.~~
  - If found equal to "FORMAT", then control is given to step 826;
  - if found equal to "PROFILE", then control is given to step 827;
  - if found equal to "TEMPLATE", then control is given to step 828.
  - 10 • if found equal to "RECELEMENT", then control is given to step 838.
  - If found equal to "RECTEMPLATE", then control is given to step 839.
- At step 826, the **EP Editor** command is issued with passing one parameter equal to the "Name" field 2232 of the unique record 2231 of the RSTMT table 2230 whose "Type" field 2237 has the "SELECTED" attribute 2242 equal to "YES", and then control is given to step 834.
- 15 • At step 827, the **EF Editor** command is issued with passing one parameter equal to the "Name" field 2232 of the unique record 2231 of the RSTMT table 2230 whose "Type" field 2237 has the "SELECTED" attribute 2242 equal to "YES", and then control is given to step 834.
- 20 • At step 828, the **ST Editor** command is issued with passing one parameter equal to the "Name" field 2232 of the unique record 2231 of the RSTMT table 2230 whose "Type" field 2237 has the "SELECTED" attribute 2242 equal to "YES", and then control is given to step 834.
- At step 829, a warning message notification is issued for informing the user that a single object must be selected within the ST Manager Dialog Box (thanks to check boxes like 212) prior clicking on the "Edit" push-button 211 or on the "Instantiate" push-button 204. This can typically be done by displaying on the display device 106 a warning message in a pop-up window, or in a status bar area, but any other similar means could be used instead, without departing from the spirit of the invention. Once the user has acknowledged this notification message through conventional means such as clicking with the pointing device 105 on an "OK" push-button present within a warning message pop-up window, or any other similar means without departing from the spirit of the invention, control is given to step 805.
- 25 • At step 830, a test is performed to determine if the local variable *RSTM\_select* is equal to 1 (one). If it is the case, then control is given to step 831; otherwise control is given to step 829.
- 30 • At step 831, a test is performed to determine the nature of the selected object, as specified by the "Type" field 2237 "NATURE" attribute 2241 of the corresponding record 2231 of the RSTMT table 2230.
- 35 • If found equal to "TEMPLATE", then control is given to step 832;
- 40 • If found equal to "RECTEMPLATE", then control is given to step 840;
- otherwise control is given to step 833.
- At step 832, the **ST Instanciator** command is issued with passing one parameter equal to the "Name" field 2232 of the unique record 2231 of the RSTMT table 2230 whose "Type" field 2237 has the "SELECTED" attribute 2242 equal to "YES", and then control is given to step 834.
- 45 • At step 833, a warning message notification is issued for informing the user that a single ST object or a single RST object must be selected within the RST Manager Dialog Box (thanks to check boxes like 212) prior clicking on the "Instantiate" push-button 204. This can typically be done by displaying on the display device 106 a warning message in a pop-up window, or in a status bar area, but any other similar means could be used instead, without departing from the spirit of the invention. Once the user has acknowledged this notification message through conventional means such as clicking
- 50

with the pointing device 105 on an "OK" push-button present within a warning message pop-up window, or any other similar means without departing from the spirit of the invention, control is given to step 805.

- 5 • At step 834, the *RST Manager* Dialog Box 200 is closed so that it disappears from the display device 106 and then control is given back to the initial step 801 for processing any future *RST Manager* command.
- 10 • At step 835, a warning message notification is issued for informing the user that at least one selected object to be deleted is referenced by another object. This can typically be done by displaying on the display device 106 a warning message in a pop-up window, or in a status bar area, but any other similar means could be used instead, without departing from the spirit of the invention. Then the user is prompted to either cancel the current "Delete" operation, or to pursue it. This can typically be done by displaying on the display device 106 a prompting message in a pop-up window, but any other similar means could be used instead, without departing from the spirit of the invention. Once the user has made his choice through conventional means such as clicking with the pointing device 105 on an "Cancel" or "Continue" push-button present within a prompting message pop-up window, or any other similar means without departing from the spirit of the invention, control is given to step 805 if the spreadsheet user decision is to cancel the "Delete" operation, or to step 809 if the spreadsheet user decision is to continue the "Delete" operation.
- 20 • At step 836, the *RE Editor* command is issued with passing one parameter ("NEW") and then control is given to step 834.
- At step 837, the *RST Editor* command is issued with passing one parameter ("NEW") and then control is given to step 834.
- 25 • At step 838, the *RE Editor* command is issued with passing one parameter equal to the "Name" field 2232 of the unique record 2231 of the RSTMT table 2230 whose "Type" field 2237 has the "SELECTED" attribute 2242 equal to "YES", and then control is given to step 834.
- 30 • At step 839, the *RST Editor* command is issued with passing one parameter equal to the "Name" field 2232 of the unique record 2231 of the RSTMT table 2230 whose "Type" field 2237 has the "SELECTED" attribute 2242 equal to "YES", and then control is given to step 834.
- At step 840, the *RST Instanciator* command is issued with passing one parameter equal to the "Name" field 2232 of the unique record 2231 of the RSTMT table 2230 whose "Type" field 2237 has the "SELECTED" attribute 2242 equal to "YES", and then control is given to step 834.
- 35 • At step 841, the value of the local variable *RSTM\_child* is updated by swapping the values "YES" and "NO". Then control is given to step 805.

## E2. EF Editor method

- 40 The method for creating or updating EF's or MEF's used in the preferred embodiment of the present invention is summarized in flowchart 900 of FIG 9. This method can be seen as the processing of the *EF Editor* command.
- At step 901, the method is in its default state, waiting for an event to initiate the process.
- 45 • At step 902, the *EF Editor* command is detected, as a result of an user action. This action can be for instance:
  - a specific combination of key on the keyboard 104, or
  - the click of the pointing device 105 on a specific button, or
  - any other similar means not further specified here.
- 50 • At step 903, the parameters of the command are retrieved. They correspond to:
  - a first mandatory parameter *EFE\_name* which can either take a reserved value "NEW" or another value corresponding to a character string name, as found in the "Name" field 2232 of a record 2231 within the RSTMT table 2230; and

- a second optional parameter *EFE\_range* which can take only two predefined values "YES" and "NO". This second optional parameter must be present when the first mandatory parameter value differs from the "NEW".

These two parameters are recorded as local variables.

- 5 • At step 904, some local variables are initialized: the local variable *EFE\_meta* is set to the value "NO", the local variable *EFE\_size* is set to the value 8 (eight).
- At step 905, a test is performed to determine the value taken by the local variable *EFE\_name*. If found equal to "NEW", then control is given to step 909; otherwise control is given to step 906.
- 10 • At step 906, the EFT table 700 is looked up to locate a record 701 whose "Name" field 702 is found equal to the value taken by the local variable *EFE\_name*. If such a record is found, then control is given to step 908; otherwise control is given to step 907.
- At step 907, an exception handler is invoked to treat this "should not occur" condition. Such operation is implementation dependent and can take different forms such as the display on the display device 106 of an error message pop-up window. Then control is given to step 925.
- 15 • At step 908,
  - the local variable *EFE\_meta* is set to the value "YES" or "NO" according to the value of the "META" attribute 708 within the "Type" field 707 of the record 701 found at step 906,
  - 20 • the local variable *EFE\_size* is set to the value found in the "Column #" field 706 of the record 701 found at step 906, and
  - the memory location pointed by the "Description Ptr" field 704 of the record 701 found at step 906 is copied onto the clipboard.
- 25 Then control is given to step 912.
- At step 909, a new name for the newly created EF or MEF is determined, according to a name string taking in a preferred embodiment of the present invention the form "New XX" where XX corresponds to a counter value ensuring the name uniqueness with respect to all the names previously defined and recorded in the "Name" fields 702, 712, 722, 2212 and 2222 found in the respective records 701, 711, 721, 2211 and 2221 of the respective tables EFT 700, EPT 710, STT 720, RET 2210 and RSST 2220. Any other similar conventional means could be used instead without departing from the spirit of the invention, as long as the uniqueness of the newly created name is ensured.
- 30 Then the new name is recorded in the local variable *EFE\_name*. Then memory space is allocated within the main memory 102 to later record the illustrative range of cells for the EF or MEF. This allocated memory is part of the memory space corresponding to the currently opened electronic spreadsheet file.
- 35 Then a new record 701 is created in the EFT table 700, and this new record 701 is initialized as follows:
  - 40 • the "Name" field 702 is set to the value of the local variable *EFE\_name* ;
  - the "Last Change Date" field 703 is set to the system time reference, as known by the central processor 101 ;
  - the "Description Ptr" field 704 is set to the memory location which has just been allocated ;
  - 45 • the "Row #" field 705 is set to the value 1 (as in the preferred embodiment of the present invention the ST's are managed in a 2D environment; this field would carry the number of defined rows for the created EF or MEF in a 3D environment) ;
  - the "Column #" field 706 is set to the value of the local variable *EFE\_size* ; and
  - 50 • the "Type" field 707 is set as follows: the attribute "META" 708 is set equal to the value of the local variable *EFE\_meta*, and the attribute "REFERENCED" 709 is initialized as follows:
    - The "OWN REFERENCE" (OR) subfield 709a is initialized with a prime number not yet assigned to any other OR subfield 709a, or 719a, or 729a, or 780a, or 2219a, or

**2229a**, or **2240a**. Various conventional techniques can be used for identifying a prime number, and are not further detailed here.

- The "FILIAION REFERENCE" (FR) subfield **709b** is initialized with the value 1 (one).
- The "INSTANCE REFERENCE" (IR) subfield **709c** is initialized with the value 1 (one).
- The "REFERENCED OBJECT" (RO) subfield **709d** is initialized with the following formula, where the P set corresponds to the set of ST's:

RO = "YES" if  $\text{LCM}(\{\text{FR}_i\})_{i \in P} \bmod \text{OR} = 0$ ;

RO = "NO" otherwise.

- The "SELECTED CHILDREN" (SC) subfield **709e** is initialized with the following formula, where the S set corresponds to the set of selected objects (having the "SELECTED" attribute **2242** equal to the value "YES" in the RSTMT table **2230**):

SC = "YES" if  $\text{LCM}(\{\text{FR}_i\})_{i \in S} \bmod \text{OR} = 0 \# \text{OR} \# \text{EFE\_name} \in S$ ;

SC = "NO" otherwise.

Then control is given to step **910**.

- At step **910**, a test is performed to determine the value taken by the local variable *EFE\_range*. If found equal to "YES", then control is given to step **911**; otherwise control is given to step **912**.
- At step **911**, the currently selected range of cells is copied onto the clipboard and the local variable *EFE\_size* is set equal to the number of columns of the selected range.
- At step **912**, the "Editor Space" sheet **315** is made the current sheet and the content of the clipboard is pasted on this blank sheet at a fixed cell address **314** (address B2 in a preferred embodiment of the present invention, as shown on FIG 3), so that the user can visualize on the display device **106** an illustration of the EF or MEF.
- At step **913**, the EF Editor Dialog Box **301** is displayed on the display device **106**. The label box **304** is initialized with the value of the local variable *EFE\_name*.
  - The top (respectively bottom) option button **310** is filled with a black point if the local variable *EFE\_meta* is found equal to "NO" (respectively "YES").
  - The text box **306** is filled with the value of the local variable *EFE\_size*.
  - The push-buttons "Save" **312** and "Save & Refresh" **308** are enabled if the local variable *EFE\_size* is found equal to the "Column #" field **706** of the current record **701**, or if the attribute "REFERENCED" **709** within the "Type" field **707** of this same record **701** is found with the subfield "REFERENCED OBJECT" **709d** (RO) equal to "NO", so that any future click with the pointing device **105** on one of these two push-buttons "Save" **312** and "Save & Refresh" **308** will be recognized as a valid event.
- The push-buttons "Save" **312** and "Save & Refresh" **308** are disabled otherwise (local variable *EFE\_size* is not found equal to the "Column #" field **706** of the current record **701**, and the attribute "REFERENCED" **709** within the "Type" field **707** of this same record **701** is found with the subfield "REFERENCED OBJECT" **709d** (RO) equal to "YES"), so that any future click with the pointing device **105** on one of these two push-buttons "Save" **312** and "Save & Refresh" **308** will not be recognized as an event.
- At step **914**, the method is waiting for any user action on the EF Editor Dialog Box **301**. Such user action is typically resulting from a click with the pointing device **105**, but take other similar forms such as, but not limited to a specific combination of key on the keyboard **104**, or any other similar means not further specified here.
- At step **915**, a user action on the EF Editor Dialog Box **301** is detected.
  - If the user action is a click on the push-button "Save & Refresh" **308**, then control is given to step **916**;
  - if the user action is a click on the push-button "Save" **312**, then control is given to step **917**;
  - if the user action is a click on the push-button "Save As" **311**, then control is given to step **918**;



- if the user action is a click on the push-button "Clear" 309, then control is given to step 919;
- if the user action is a click on the spin button 307, then control is given to step 920;
- if the user action is a click on one of the two option buttons 310, then control is given to step 921;
- if the user action is a click on the push-button "Done" 303, or on the closing-window push-button 302, then control is given to step 925.
- At step 916, the EFT table 700 is updated and saved as part of the electronic spreadsheet file by refreshing the record 701 whose "Name" field 702 is equal to the local variable *EFE\_name*. For this purpose,
  - the "Last Change Date" field 703 is set to the system time reference, as known by the central processor 101 ;
  - the "Column #" field 706 is set to the value of the local variable *EFE\_size* ; and
  - the "Type" field 707 is set as follows: the attribute "META" 708 is set equal to the value of the local variable *EFE\_meta*.

In addition the range of cells 314 illustrating on the "Editor Space" sheet 315 the current definition of the EF or MEF is copied onto the memory location pointed by the "Description Ptr" field 704. Then control is given to step 922.
- At step 917, the EFT table 700 is updated and saved as part of the electronic spreadsheet file by refreshing the record 701 whose "Name" field 702 is equal to the local variable *EFE\_name*. For this purpose,
  - the "Last Change Date" field 703 is set to the system time reference, as known by the central processor 101 ;
  - the "Column #" field 706 is set to the value of the local variable *EFE\_size* ; and
  - the "Type" field 707 is set as follows: the attribute "META" 708 is set equal to the value of the local variable *EFE\_meta*.

In addition the range of cells 314 illustrating on the "Editor Space" sheet 315 the current definition of the EF or MEF is copied onto the memory location pointed by the "Description Ptr" field 704. Then control is given to step 913.
- At step 918, a test is performed on the value found in the text box 305 to determine if it corresponds to a valid new name. The corresponding criteria are implementation dependent and may take different forms without departing from the spirit of the invention, as long as the new proposed name is a unique character string against all the already defined names recorded in the "Name" fields 702, 712, 722, 2212 and 2222. If validity and uniqueness are proven, then control is given to step 923; otherwise control is given to step 924.
- At step 919, the default attributes currently defined in the spreadsheet environment are applied to the "Editor Space" sheet 315, so that the displayed illustration of the EF or MEF receives these same default attributes. Then control is given to the step 913.
- At step 920, the local variable *EFE\_size* is either incremented or decremented by 1 (one) according to the direction (up or down) specified by the pointing device 105 on the spin button 307, and as long as its value remains positive and less than or equal to an upper limit set equal to 254 in a preferred embodiment of the present invention. Then control is given to step 913.
- At step 921, the local variable *EFE\_meta* is updated, so that its value becomes "yes" (respectively "no") if the bottom (respectively top) option button 310 has been clicked on. Then control is given to step 913.
- At step 922, the **ST Refresh Manager** command is issued with the following parameters: *EFE\_name*, "FORMAT" and then control is given to step 913.
- At step 923, memory space is allocated within the main memory 102 to later record the illustrative range of cells for the EF or MEF. This allocated memory is part of the memory space corresponding to the currently opened electronic spreadsheet file. Then a new

record **701** is created in the EFT table **700** which is saved as part of the electronic spreadsheet file, and this new record **701** is initialized as follows:

- the "Name" field **702** is set to the value found in the text box **305** and validated at step **918**; this field **702** becoming then the new value of the *EFE\_name* local variable;
- the "Last Change Date" field **703** is set to the system time reference, as known by the central processor **101** ;
- the "Description Ptr" field **704** is set to the memory location which has just been allocated ;
- the "Row #" field **705** is set to the value 1 (as in the preferred embodiment of the present invention the ST's are managed in a 2D environment; this field would carry the number of defined rows for the created EF or MEF in a 3D environment) ;
- the "Column #" field **706** is set to the value of the local variable *EFE\_size* ; and
- the "Type" field **707** is set as follows: the attribute "META" **708** is set equal to the value of the local variable *EFE\_meta*, and the attribute "REFERENCED" **709** is initialized as follows:
  - The "OWN REFERENCE" (OR) subfield **709a** is initialized with a prime number not yet assigned to any other OR subfield **709a**, or **719a**, or **729a**, or **780a**, or **2219a**, or **2229a**, or **2240a**. Various conventional techniques can be used for identifying a prime number, and are not further detailed here.
  - The "FILATION REFERENCE" (FR) subfield **709b** is initialized with the value 1 (one).
  - The "INSTANCE REFERENCE" (IR) subfield **709c** is initialized with the value 1 (one).
  - The "REFERENCED OBJECT" (RO) subfield **709d** is initialized with the following formula, where the P set corresponds to the set of ST's:
 
$$RO = \text{"YES"} \text{ if } LCM(\{FR_i\})_{i \in P} \bmod OR = 0;$$

$$RO = \text{"NO"} \text{ otherwise.}$$
  - The "SELECTED CHILDREN" (SC) subfield **709e** is initialized with the following formula, where the S set corresponds to the set of selected objects (having the "SELECTED" attribute **2242** equal to the value "YES" in the RSTMT table **2230**):
 
$$SC = \text{"YES"} \text{ if } LCM(\{FR_i\})_{i \in S} \bmod OR = 0 \#OR\# EFE\_name \in S;$$

$$SC = \text{"NO"} \text{ otherwise.}$$

Then control is given to step **913**.

- At step **924**, a warning message notification is issued for informing the user that a valid and unique name must be specified in the text box **305** prior to clicking on the "Save As" push-button **311**. This can typically be done by displaying on the display device **106** a warning message in a pop-up window, or in a status bar area, but any other similar means could be used instead, without departing from the spirit of the invention. Once the user has acknowledged this notification message through conventional means such as clicking with the pointing device **105** on an "OK" push-button present within a warning message pop-up window, or any other similar means without departing from the spirit of the invention, control is given to step **913**.
- At step **925**, the EF Editor Dialog Box **501** is closed so that it disappears from the display device **106**, then the "Editor Space" sheet **515** is removed from the displayed window so that it is replaced by the original sheet present at *EF Editor* invocation time. Finally control is given back to the initial step **901** for processing any future *EF Editor* command.

### E3. EP Editor method

The method for creating or updating EP's or MEP's used in the preferred embodiment of the present invention is summarized in flowchart **1000** of FIG **10**. This method can be seen as the processing of the *EP Editor* command.

- At step **1001**, the method is in its default state, waiting for an event to initiate the process.

- At step **1002**, the *EP Editor* command is detected, as a result of an user action. This action can be for instance:
  - a specific combination of key on the keyboard **104**, or
  - the click of the pointing device **105** on a specific button, or
  - any other similar means not further specified here;
- At step **1003**, the parameters of the command are retrieved. They correspond to:
  - a first mandatory parameter *EPE\_name* which can either take a reserved value "NEW" or another value corresponding to a character string name, as found in the "Name" field **2232** of a record **2231** within the RSTMT table **2230**; and
  - a second optional parameter *EPE\_range* which can take only two predefined values "YES" and "NO". This second optional parameter must be present when the first mandatory parameter value differs from the "NEW".

These two parameters are recorded as local variables.
- At step **1004**, some local variables are initialized: the local variable *EPE\_meta* is set to the value "no", the local variable *EPE\_size* is set to the value 8 (eight).
- At step **1005**, a test is performed to determine the value taken by the local variable *EPE\_name*. If found equal to "NEW", then control is given to step **1009**; otherwise control is given to step **1006**.
- At step **1006**, the EPT table **710** is looked up to locate a record **711** whose "Name" field **712** is found equal to the value taken by the local variable *EPE\_name*. If such a record is found, then control is given to step **1008**; otherwise control is given to step **1007**.
- At step **1007**, an exception handler is invoked to treat this "should not occur" condition. Such operation is implementation dependent and can take different forms such as the display on the display device **106** of an error message pop-up window. Then control is given to step **1025**.
- At step **1008**,
  - the local variable *EPE\_meta* is set to the value "YES" or "NO" according to the value of the "META" attribute **718** within the "Type" field **717** of the record **711** found at step **1006**,
  - the local variable *EPE\_size* is set to the value found in the "Column #" field **716** of the record **711** found at step **1006**, and
  - the memory location pointed by the "Description Ptr" field **714** of the record **711** found at step **1006** is copied onto the clipboard and within the local variable *EPE\_Desc*.
- Then control is given to step **1012**.
- At step **1009**, a new name for the newly created EP or MEP is determined, according to a name string taking in a preferred embodiment of the present invention the form "New XX" where XX corresponds to a counter value ensuring the name uniqueness with respect to all the names previously defined and recorded in the "Name" fields **702**, **712**, **722**, **2212** and **2222** found in the respective records **701**, **711**, **721**, **2211** and **2221** of the respective tables EFT **700**, EPT **710**, STT **720**, RET **2210** and RSST **2220**. Any other similar conventional means could be used instead without departing from the spirit of the invention, as long as the uniqueness of the newly created name is ensured. Then the new name is recorded in the local variable *EPE\_name*.
- Then memory space is allocated within the main memory **102** to later record the illustrative range of cells for the EP or MEP. This allocated memory is part of the memory space corresponding to the currently opened electronic spreadsheet file. Then a new record **711** is created in the EPT table **710**, and this new record **711** is initialized as follows:
  - the "Name" field **712** is set to the value of the local variable *EPE\_name* ;
  - the "Last Change Date" field **713** is set to the system time reference, as known by the central processor **101** ;

- the "Description Ptr" field 714 is set to the memory location which has just been allocated ;
- the "Row #" field 715 is set to the value 1 (as in the preferred embodiment of the present invention the ST's are managed in a 2D environment; this field would carry the number of defined rows for the created EP or MEP in a 3D environment) ;
- the "Column #" field 716 is set to the value of the local variable *EPE\_size* ; and
- the "Type" field 717 is set as follows: the attribute "META" 718 is set equal to the value of the local variable *EPE\_meta*, and the attribute "REFERENCED" 719 is initialized as follows:

- The "OWN REFERENCE" (OR) subfield 719a is initialized with a prime number not yet assigned to any other OR subfield 709a, or 719a, or 729a, or 780a, or 2219a, or 2229a, or 2240a. Various conventional techniques can be used for identifying a prime number, and are not further detailed here.
- The "FILATION REFERENCE" (FR) subfield 719b is initialized with the value 1 (one).
- The "INSTANCE REFERENCE" (IR) subfield 719c is initialized with the value 1 (one).
- The "REFERENCED OBJECT" (RO) subfield 719d is initialized with the following formula, where the P set corresponds to the set of ST's:

$$RO = \text{"YES"} \text{ if } LCM(\{FR_i\})_{i \in P} \bmod OR = 0;$$

$$RO = \text{"NO"} \text{ otherwise.}$$

- The "SELECTED CHILDREN" (SC) subfield 719e is initialized with the following formula, where the S set corresponds to the set of selected objects (having the "SELECTED" attribute 2242 equal to the value "YES" in the RSTMT table 2230):

$$SC = \text{"YES"} \text{ if } LCM(\{FR_i\})_{i \in S} \bmod OR = 0 \text{ \#OR\# } EPE\_name \in S;$$

$$SC = \text{"NO"} \text{ otherwise.}$$

Then control is given to step 1010.

- At step 1010, a test is performed to determine the value taken by the local variable *EPE\_range*. If found equal to "YES", then control is given to step 1011; otherwise control is given to step 1012.
- At step 1011, the currently selected range of cells is copied onto the clipboard and the local variable *EPE\_size* is set equal to the number of columns of the selected range.
- At step 1012, the "Editor Space" sheet 315 is made the current sheet and the content of the clipboard is pasted on this blank sheet at a fixed cell address 314 (address B2 in a preferred embodiment of the present invention, as shown on FIG 3), so that the user can visualize on the display device 106 an illustration of the EP or MEP.
- At step 1013, the EP Editor Dialog Box 401 is displayed on the display device 106.
  - The label box 404 is initialized with the value of the local variable *EPE\_name*. The top (respectively bottom) option button 410 is filled with a black point if the local variable *EPE\_meta* is found equal to "No" (respectively "Yes").
  - The text box 406 is filled with the value of the local variable *EPE\_size*.
  - The push-buttons "Save" 412 and "Save & Refresh" 408 are enabled if the local variable *EPE\_size* is found equal to the "Column #" field 716 of the current record 711, or if the attribute "REFERENCED" 719 within the "Type" field 717 of this same record 711 is found with the subfield "REFERENCED OBJECT" 719d (RO) equal to "NO", so that any future click with the pointing device 105 on one of these two push-buttons "Save" 412 and "Save & Refresh" 408 will be recognized as a valid event.
  - The push-buttons "Save" 412 and "Save & Refresh" 408 are disabled otherwise (local variable *EPE\_size* is not found equal to the "Column #" field 716 of the current record 711, and the attribute "REFERENCED" 719 within the "Type" field 717 of this same record 711 is found with the subfield "REFERENCED OBJECT" 719d (RO) equal to "YES"), so that any future click with the pointing device 105 on one of these two push-buttons "Save" 412 and "Save & Refresh" 408 will not be recognized as an event.

- At step 1014, the method is waiting for any user action on the EP Editor Dialog Box 401. Such user action is typically resulting from a click with the pointing device 105, but take other similar forms such as, but not limited to a specific combination of key on the keyboard 104, or any other similar means not further specified here.
- 5 • At step 1015, a user action on the EP Editor Dialog Box 401 is detected:
  - If the user action is a click on the push-button "Save & Refresh" 408, then control is given to step 1016;
  - if the user action is a click on the push-button "Save" 412, then control is given to step 1017;
  - 10 • if the user action is a click on the push-button "Save As" 411, then control is given to step 1018;
  - if the user action is a click on the push-button "Clear" 409, then control is given to step 1019;
  - if the user action is a click on the spin button 407, then control is given to step 1020;
  - 15 • if the user action is a click on one of the two option buttons 410, then control is given to step 1021;
  - if the user action is a click on the push-button "Done" 403, or on the closing-window push-button 402, then control is given to step 1025.
- 20 • At step 1016, the EPT table 710 is updated and saved as part of the electronic spreadsheet file by refreshing the record 711 whose "Name" field 712 is equal to the local variable *EPE\_name*. For this purpose,
  - the "Last Change Date" field 713 is set to the system time reference, as known by the central processor 101 ;
  - the "Column #" field 716 is set to the value of the local variable *EPE\_size* ; and
  - 25 • the "Type" field 717 is set as follows: the attribute "META" 718 is set equal to the value of the local variable *EPE\_meta*.

In addition the range of cells 414 illustrating on the "Editor Space" sheet 415 the current definition of the EP or MEP is copied onto the memory location pointed by the "Description Ptr" field 714. Then control is given to step 1022.
- 30 • At step 1017, the EPT table 710 is updated and saved as part of the electronic spreadsheet file by refreshing the record 711 whose "Name" field 712 is equal to the local variable *EPE\_name*. For this purpose,
  - the "Last Change Date" field 713 is set to the system time reference, as known by the central processor 101 ;
  - 35 • the "Column #" field 716 is set to the value of the local variable *EPE\_size* ; and
  - the "Type" field 717 is set as follows: the attribute "META" 718 is set equal to the value of the local variable *EPE\_meta*.

In addition the range of cells 414 illustrating on the "Editor Space" sheet 415 the current definition of the EP or MEP is copied onto the memory location pointed by the "Description Ptr" field 714.
- 40 Then the local variable *EPE\_desc* is updated with the current EP or MEP description, as recorded in the memory location pointed by the "Description Ptr" field 714, and control is given to step 1013.
- At step 1018, a test is performed on the value found in the text box 405 to determine if this value corresponds to a valid new name. The corresponding criteria are implementation dependent and may take different forms without departing from the spirit of the invention, as long as the new proposed name is a unique character string against all the already defined names recorded in the "Name" fields 702, 712, 722, 2212 and 2222. If validity and uniqueness are proven, then control is given to step 1023; otherwise
- 50 control is given to step 1024.
- At step 1019, the default attributes currently defined in the spreadsheet environment are applied to the "Editor Space" sheet 415, so that the displayed illustration of the EP or MEP receives these same default attributes. Then control is given to the step 1013.

- At step **1020**, the local variable *EPE\_size* is either incremented or decremented by 1 (one) according to the direction (up or down) specified by the pointing device **105** on the spin button **407**, and as long as its value remains positive and less than or equal to an upper limit set equal to 254 in a preferred embodiment of the present invention. Then control is given to step **1013**.
  - At step **1021**, the local variable *EPE\_meta* is updated, so that its value becomes "yes" (respectively "no") if the bottom (respectively top) option button **410** has been clicked on. Then control is given to step **1013**.
  - At step **1022**, the **ST Refresh Manager** command is issued with the following parameters: *EPE\_name*, "PROFILE", and *EPE\_desc*. Then the local variable *EPE\_desc* is updated with the current EP or MEP description, as recorded in the memory location pointed by the "Description Ptr" field **714** and then control is given to step **1013**.
  - At step **1023**, memory space is allocated within the main memory **102** to later record the illustrative range of cells for the EP or MEP. This allocated memory is part of the memory space corresponding to the currently opened electronic spreadsheet file. Then a new record **711** is created in the EPT table **710** which is saved as part of the electronic spreadsheet file, and this new record **711** is initialized as follows:
    - the "Name" field **712** is set to the value found in the text box **405** and validated at step **1018**; this field **712** becoming then the new value of the *EPE\_name* local variable;
    - the "Last Change Date" field **713** is set to the system time reference, as known by the central processor **101**;
    - the "Description Ptr" field **714** is set to the memory location which has just been allocated;
    - the "Row #" field **715** is set to the value 1 (as in the preferred embodiment of the present invention the ST's are managed in a 2D environment; this field would carry the number of defined rows for the created EP or MEP in a 3D environment);
    - the "Column #" field **716** is set to the value of the local variable *EPE\_size*;
    - the "Type" field **717** is set as follows: the attribute "META" **718** is set equal to the value of the local variable *EPE\_meta*, and the attribute "REFERENCED" **719** is initialized as follows:
      - The "OWN REFERENCE" (OR) subfield **719a** is initialized with a prime number not yet assigned to any other OR subfield **709a**, or **719a**, or **729a**, or **780a**, or **2219a**, or **2229a**, or **2240a**. Various conventional techniques can be used for identifying a prime number, and are not further detailed here.
      - The "FILATION REFERENCE" (FR) subfield **719b** is initialized with the value 1 (one).
      - The "INSTANCE REFERENCE" (IR) subfield **719c** is initialized with the value 1 (one).
      - The "REFERENCED OBJECT" (RO) subfield **719d** is initialized with the following formula, where the P set corresponds to the set of ST's:
 
$$RO = \text{"YES"} \text{ if } LCM(\{FR_i\})_{i \in P} \bmod OR = 0;$$

$$RO = \text{"NO"} \text{ otherwise.}$$
      - The "SELECTED CHILDREN" (SC) subfield **719e** is initialized with the following formula, where the S set corresponds to the set of selected objects (having the "SELECTED" attribute **2242** equal to the value "yes" in the RSTMT table **2230**):
 
$$SC = \text{"YES"} \text{ if } LCM(\{FR_i\})_{i \in S} \bmod OR = 0 \#OR\# EPE\_name \in S;$$

$$SC = \text{"NO"} \text{ otherwise.}$$
- Then control is given to step **1013**.
- At step **1024**, a warning message notification is issued for informing the user that a valid and unique name must be specified in the text box **405** prior to clicking on the "Save As" push-button **411**. This can typically be done by displaying on the display device **106** a warning message in a pop-up window, or in a status bar area, but any other similar means could be used instead, without departing from the spirit of the invention. Once the user has acknowledged this notification message through conventional means such as clicking with the pointing device **105** on an "OK" push-button present within a warning



message pop-up window, or any other similar means without departing from the spirit of the invention, control is given to step 1013.

- At step 1025, the EP Editor Dialog Box 401 is closed so that it disappears from the display device 106, then the "Editor Space" sheet 415 is removed from the display window so that it is replaced by the original sheet present at EP Editor invocation time. Finally control is given back to the initial step 1001 for processing any future EP Editor command.

#### E4. ST Editor method

The method for creating or updating ST's used in the preferred embodiment of the present invention is summarized in flowchart 1100 of FIG 11. This method can be seen as the processing of the **ST Editor** command.

- At step 1101, the method is in its default state, waiting for an event to initiate the process.
- At step 1102, the **ST Editor** command is detected, as a result of an user action. This action can be for instance:
  - a specific combination of key on the keyboard 104, or
  - the click of the pointing device 105 on a specific button, or
  - any other similar means not further specified here.
- At step 1103, the parameter of the command is retrieved. It corresponds to a mandatory parameter *STE\_name* which can either take a reserved value "NEW" or another value corresponding to a character string name, as found in the "Name" field 2232 of a record 2231 within the RSTMT table 2230. This parameter is recorded as a local variable.
- At step 1104, some local variables are initialized: the local variable *STE\_min* is set to the default value 1 (one), the local variable *STE\_max* is set to the default value 255.
- At step 1105, a test is performed to determine the value taken by the local variable *STE\_name*. If found equal to "NEW", then control is given to step 1109; otherwise control is given to step 1106.
- At step 1106, the STT table 720 is looked up to locate a record 721 whose "Name" field 722 is found equal to the value taken by the local variable *STE\_name*. If such a record is found, then control is given to step 1108; otherwise control is given to step 1107.
- At step 1107, an exception handler is invoked to treat this "should not occur" condition. Such operation is implementation dependent and can take different forms such as the display on the display device 106 of an error message pop-up window. Then control is given to step 1128.
- At step 1108,
  - the local variable *STE\_min* is set to the value found in the "Min Element #" field 725 of the record 721 found at step 1106,
  - the local variable *STE\_max* is set to the value found in the "Max Element #" field 726 of the record 721 found at step 1106.
- Then the memory location pointed by the "Description Ptr" field 724 of the record 721 found at step 1106 (where is recorded the description of the ST according to the STDT table 760 illustrated in FIG 7D) is copied in a working buffer which in turns follows the same STDT table 760. This structure is then used to build on the clipboard within the main memory 102 a spreadsheet range of cells illustrating the ST definition copied in the working buffer. This construction is achieved by loading in the clipboard within the main memory 102 an ordered sequence of ranges of cells, each of them successively abiding by the EF (column 765) and the EP (column 764) definition corresponding to each pair of EF and EP names, starting with the first pair 761 up to the last one 763. Then control is given to step 1110.
- At step 1109, a new name for the newly created ST is determined, according to a name string taking in a preferred embodiment of the present invention the form "New XX" where XX corresponds to a counter value ensuring the name uniqueness with respect to all the names previously defined and recorded in the "Name" fields 702, 712, 722, 2212

and 2222 found in the respective records 701, 711, 721, 2211 and 2221 of the respective tables EFT 700, EPT 710, STT 720, RET 2210 and RSST 2220. Any other similar conventional means could be used instead without departing from the spirit of the invention, as long as the uniqueness of the newly created name is ensured. Then the new name is recorded in the local variable *STE\_name*. Then memory space is allocated within the main memory 102 to later record the illustrative range of cells for the new ST. This allocated memory is part of the memory space corresponding to the currently opened electronic spreadsheet file and follows the STDT table 760 illustrated in FIG 7D. Then a new record 721 is created in the STT table 720, and this new record 721 is initialized as follows:

- the "Name" field 722 is set to the value of the local variable *STE\_name* ;
- the "Last Change Date" field 723 is set to the system time reference, as known by the central processor 101 ;
- the "Description Ptr" field 724 is set to the memory location which has just been allocated ;
- the "Min Element #" field 725 is set to the value of the local variable *STE\_min*;
- the "Max Element #" field 726 is set to the value of the local variable *STE\_max* ; and
- the "Type" field 727 is set as follows: the attribute "META" 728 is set equal to "NO", and the attribute "REFERENCED" 729 is initialized as follows:

- The "OWN REFERENCE" (OR) subfield 729a is initialized with a prime number not yet assigned to any other OR subfield 709a, or 719a, or 729a, or 780a, or 2219a, or 2229a, or 2240a. Various conventional techniques can be used for identifying a prime number, and are not further detailed here.

- The "FILATION REFERENCE" (FR) subfield 729b is initialized according to the following formula, where the F set corresponds to the set of EF's, MEF's, EP's and MEP's constituting the new ST, according to the structure recorded in the "Description Ptr" field 724:

$$FR = \prod_{i \in F} OR_i \times LCM(\{FR_i\})_{i \in F}$$

- The "INSTANCE REFERENCE" (IR) subfield 729c is initialized with the value 1 (one).
- The "REFERENCED OBJECT" (RO) subfield 729d is initialized with the following formula, where the P set corresponds to the set of RE's and RME's:

$$RO = \text{"YES"} \text{ if } LCM(\{FR_i\})_{i \in P} \bmod OR = 0;$$

$$RO = \text{"NO"} \text{ otherwise.}$$

- The "SELECTED CHILDREN" (SC) subfield 729e is initialized with the following formula, where the S set corresponds to the set of selected objects (having the "SELECTED" attribute 2242 equal to the value "YES" in the RSTMT table 2230):

$$SC = \text{"YES"} \text{ if } LCM(\{FR_i\})_{i \in S} \bmod OR = 0 \text{ \#OR\# } STE\_name \in S;$$

$$SC = \text{"NO"} \text{ otherwise.}$$

Then a working buffer is allocated in main memory 102 and initialized with a default ST description which corresponds to a single pair 762 of default EF and default EP. This default ST description is then used to build on the clipboard within the main memory 102 a spreadsheet range of cells illustrating the new ST. This construction is achieved as explained at the end of the step 1108. Then control is given to step 1110.

- At step 1110, the "Editor Space" sheet 515 is made the current sheet and this sheet is turned to write-protect mode while regular row insertion and deletion are disabled. Then the top left cell of the range of cells 514 is selected. Then the local variable *STE\_format* is filled with the name of the EF or of the MEF corresponding to the row where is located the currently selected cell within the range of cells 514. Finally the local variable *STE\_profile* is filled with the name of the EP or of the MEP corresponding to the row where is located the currently selected cell within the range of cells 514.
- At step 1111, the ST Editor Dialog Box 501 is displayed on the display device 106. The label box 504 is initialized with the value of the local variable *STE\_name*. The text box 506 is filled with the value of the local variable *STE\_min*.

The text box 509 is filled with the value of the local variable *STE\_max*.

The combo box 511 is filled with the value of the local variable *STE\_format*.

The combo box 510 is filled with the value of the local variable *STE\_profile*.

- Then the range of cells 514 is updated according to the description recorded in the memory-clipboard: the content of the clipboard is pasted on this blank sheet at a fixed cell address 514 (address B2 in a preferred embodiment of the present invention, as shown on FIG 5), so that the user can visualize on the display device 106, within the window 500 an illustration of the ST. Then a test is performed to check if all the EF's, EP's, MEF's and MEP's contributing to the ST definition illustrated by the range of cells 514, have the same number of fields. If it is the case, then the two push-buttons "Save" 513 and "Save As" 512 are enabled, so that the click with the pointing device 105 on one of these two push-buttons is recognized as a valid event. Otherwise the two push-buttons "Save" 513 and "Save As" 512 are disabled, so that the click with the pointing device 105 on one of these two push-buttons is not recognized as a valid event.
- At step 1112, the method is waiting for any user action on the ST Editor Dialog Box 501. Such user action is typically resulting from a click with the pointing device 105, but take other similar forms such as, but not limited to a specific combination of key on the keyboard 104, or any other similar means not further specified here.
  - At step 1113, a user action on the ST Editor Dialog Box 501 is detected.
    - If the user action is a click on the push-button "Save" 513, then control is given to step 1116;
    - If the user action is a click on the push-button "Save As" 512, then control is given to step 1119;
    - If the user action is a click on the push-button "Add" 517, then control is given to step 1124;
    - If the user action is a click on the push-button "Delete" 518, then control is given to step 1125;
    - If the user action is a click on the push-button "Up" 519 or on the push-button "Down" 520, then control is given to step 1126;
    - If the user action is an update of the combo box 511, then control is given to step 1114;
    - If the user action is an update of the combo box 510, then control is given to step 1115;
    - If the user action is a click on the spin button 507, then control is given to step 1122;
    - If the user action is a click on the spin button 508, then control is given to step 1123;
    - If the user action is a click on the push-button "Done" 503, or on the closing-window push-button 502, then control is given to step 1128.
  - At step 1114, the ST description is updated in the working buffer by replacing by the EF or MEF name found in the text box 511 the previous EF or MEF specification corresponding to the element or meta-element illustrated by the currently selected cell within the range of cells 514. Then the local variable *STE\_format* is also set equal to the name found in the text box 511. Then control is given to step 1111.
  - At step 1115, the ST description is updated in the working buffer by replacing by the EP or MEP name found in the text box 510 the previous EP or MEP specification corresponding to the element or meta-element illustrated by the currently selected cell within the range of cells 514. Then the local variable *STE\_profile* is also set equal to the name found in the text box 510. Then control is given to step 1111.
  - At step 1116, a test is performed to check if the currently edited ST is already referenced by an existing RE or RME or is already instantiated as a STI. For this purpose is considered the "REFERENCED" attribute 729 within the "Type" field 727 of the record 721 within the STT table 720 whose "Name" field 722 is equal to the local variable *STE\_name*. If the value of the "REFERENCED OBJECT" (RO) subfield 729d is equal

to "No" and if the value of the "INSTANCE REFERENCE" (IR) subfield 729c is equal to 1 (one), then control is given to step 1117; otherwise control is given to step 1118.

- At step 1117, the STT table 720 is updated by refreshing the record 721 whose "Name" field 722 is equal to the local variable *STE\_name*. For this purpose,
  - the "Last Change Date" field 723 is set to the system time reference, as known by the central processor 101 ;
  - the "Min Element #" field 725 is set to the value of the local variable *STE\_min*;
  - the "Max Element #" field 726 is set to the value of the local variable *STE\_max*.
  - The current description of the ST, as illustrated by the range of cells 514, as recorded in the working buffer, and following the STDT table 760 is copied onto the memory location pointed by the "Description Ptr" field 724.
  - The "Type" field 727 is updated as the "FILATION REFERENCE" (FR) subfield 729b of the "REFERENCED" attribute 729 is automatically updated thanks to its definition formula depending on the set of EF's, MEF's, EP's and MEP's belonging to the STDT table 760 pointed by the "Description Ptr" field 724.
  - For each EF name or MEF name found in the column 765 of this STDT table 760, the EFT table 700 is automatically updated within the corresponding records 701 whose "Name" field 702 matches this element or MEF name, as the subfield "REFERENCED OBJECT" (RO) 709d (within the "REFERENCED" attribute 709) is recalculated according to its definition formula.
  - For each EP name or MEP name found in the column 764 of this STDT table 760, the EPT table 710 is automatically updated within the corresponding records 711 whose "Name" field 712 matches this element or MEP name, as the subfield "REFERENCED OBJECT" (RO) 719d (within the "REFERENCED" attribute 719) is recalculated according to its definition formula.

Then control is given to step 1111.

- At step 1118, a warning message notification is issued for informing the user that the edited ST is already referenced by a RE or RME or is already instanciated as an existing STI. This can typically be done by displaying on the display device 106 a warning message in a pop-up window, or in a status bar area, but any other similar means could be used instead, without departing from the spirit of the invention. Then the user is prompted to either cancel the current "Save" operation, or to pursue it. This can typically be done by displaying on the display device 106 a prompting message in a pop-up window, but any other similar means could be used instead, without departing from the spirit of the invention. Once the user has made his choice through conventional means such as clicking with the pointing device 105 on an "Cancel" or "Continue" push-button present within a prompting message pop-up window, or any other similar means without departing from the spirit of the invention, control is given to step 1111 if the spreadsheet user decision is to cancel the operation, or to step 1117 if the spreadsheet user decision is to continue the operation.
- At step 1119, a test is performed on the value found in the text box 505 to determine if it corresponds to a valid new name. The corresponding criteria are implementation dependent and may take different forms without departing from the spirit of the invention, as long as the new proposed name is a unique character string against all the already defined names recorded in the "Name" fields 702, 712, 722, 2212 and 2222. If validity and uniqueness are proven, then control is given to step 1120; otherwise control is given to step 1121.
- At step 1120, memory space is allocated within the main memory 102 to later record the descriptor of the ST. This allocated memory is part of the memory space corresponding to the currently opened electronic spreadsheet file. Then a new record 721 is created in the STT table 720, and this new record 721 is initialized as follows:

- the "Name" field 722 is set to the value found in the text box 505 and validated at step 1119; this field 722 becoming then the new value of the *STE\_name* local variable;
- the "Last Change Date" field 723 is set to the system time reference, as known by the central processor 101;
- the "Description Ptr" field 724 is set to the memory location which has just been allocated;
- the "Min Element #" field 725 is set to the value of the local variable *STE\_min*;
- the "Max Element #" field 726 is set to the value of the local variable *STE\_max*;
- the current description of the ST, as illustrated by the range of cells 514, as recorded in the working buffer, and following the STDT table 760 is copied onto the memory location pointed by the "Description Ptr" field 724.
- the "Type" field 727 is set as follows: the attribute "META" 728 is set equal to "no", and the attribute "REFERENCED" 729 is initialized as follows:

- The "OWN REFERENCE" (OR) subfield 729a is initialized with a prime number not yet assigned to any other OR subfield 709a, or 719a, or 729a, or 780a, or 2219a, or 2229a, or 2240a. Various conventional techniques can be used for identifying a prime number, and are not further detailed here.

- The "FILATION REFERENCE" (FR) subfield 729b is initialized according to the following formula, where the F set corresponds to the set of EF's, MEF's, EP's and MEP's constituting the new ST, according to the structure recorded in the "Description Ptr" field 724:

$$FR = \prod_{i \in F} OR_i \times LCM(\{FR_i\})_{i \in F}$$

- The "INSTANCE REFERENCE" (IR) subfield 729c is initialized with the value 1 (one).
- The "REFERENCED OBJECT" (RO) subfield 729d is initialized with the following formula, where the P set corresponds to the set of RE's and RME's:

$$RO = \text{"YES"} \text{ if } LCM(\{FR_i\})_{i \in P} \bmod OR = 0;$$

$$RO = \text{"NO"} \text{ otherwise.}$$

- The "SELECTED CHILDREN" (SC) subfield 729e is initialized with the following formula, where the S set corresponds to the set of selected objects (having the "SELECTED" attribute 2242 equal to the value "YES" in the RSTMT table 2230):

$$SC = \text{"YES"} \text{ if } LCM(\{FR_i\})_{i \in S} \bmod OR = 0 \text{ \#OR\# } STE\_name \in S;$$

$$SC = \text{"NO"} \text{ otherwise.}$$

- For each EF name or MEF name found in the column 765 of this STDT table 760, the EFT table 700 is automatically updated within the corresponding records 701 whose "Name" field 702 matches this element or MEF name, as the subfield "REFERENCED OBJECT" (RO) 709d (within the "REFERENCED" attribute 709) is recalculated according to its definition formula.
- For each EP name or MEP name found in the column 764 of this STDT table 760, the EPT table 710 is automatically updated within the corresponding records 711 whose "Name" field 712 matches this element or MEP name, as the subfield "REFERENCED OBJECT" (RO) 719d (within the "REFERENCED" attribute 719) is recalculated according to its definition formula.

Then control is given to step 1111.

- At step 1121, a warning message notification is issued for informing the user that a valid and unique name must be specified in the text box 505 prior to clicking on the "Save As" push-button 512. This can typically be done by displaying on the display device 106 a warning message in a pop-up window, or in a status bar area, but any other similar means could be used instead, without departing from the spirit of the invention. Once the user has acknowledged this notification message through conventional means such as clicking with the pointing device 105 on an "OK" push-button present within a warning message pop-up window, or any other similar means without departing from the spirit of the invention, control is given to step 1111.

- At step 1122, the local variable *STE\_min* is either incremented or decremented by 1 (one) according to the direction (up or down) specified by the pointing device 105 on the spin button 507, and as long as its value remains positive and less than or equal to both an upper limit set equal to 254 in a preferred embodiment of the present invention and to the value shown in the text box 509. Then control is given to step 1111.
- At step 1123, the local variable *STE\_max* is either incremented or decremented by 1 (one) according to the direction (up or down) specified by the pointing device 105 on the spin button 508, and as long as its value remains positive, greater than the value shown in the text box 506 and less than or equal to an upper limit set equal to 254 in a preferred embodiment of the present invention. Then control is given to step 1111.
- At step 1124, a new row is inserted in the range of cells 514 illustrating the edited ST, above the row where the last selected cell was previously located. Then the left most cell located on the new row within the range of cells 514 is selected. Then the ST definition is updated in the working buffer by introducing a new meta-element which is described, like the other ones, by a couple (MEF 765, MEP 764) which defaults to a couple of default MEF and default MEP, which are also respectively assigned to the local variable *STE\_format* and *STE\_profile*. In addition the current description of the ST, as illustrated by the range of cells 514, as recorded in the working buffer, and following the STDT table 760 is copied onto the memory location pointed by the "Description Ptr" field 724. Then control is given to step 1111.
- At step 1125, the row containing the selected cell is removed from the range of cells 514. Then the left most cell located within the range of cells 514 on the row representing the element defined within the edited ST is selected. Then the ST definition is updated by removing the deleted meta-element which was described by a couple (MEF, MEP). In addition the current description of the ST, as illustrated by the range of cells 514, as recorded in the working buffer, and following the STDT table 760 is copied onto the memory location pointed by the "Description Ptr" field 724. Then control is given to step 1127.
- At step 1126, the current cell within the "Editor Space" sheet 515 is respectively moved up or down if the spreadsheet user has clicked with the pointing device 105 on the "Up" push-button 519, or on the "Down" push-button 520, and also if this movement does not move the current cell away from the range of cells 514 illustrating the ST.
- At step 1127, the local variables *STE\_format* and *STE\_profile* are respectively set equal to the name of the EF or MEF and to the name of the EP or MEP corresponding to the element or the meta-element illustrated by the currently selected cell within the range of cells 514. Then control is given to step 1111.
- At step 1128, the ST Editor Dialog Box 501 is closed so that it disappears from the display device 106, then the "Editor Space" sheet 515 is removed from the display window so that it is replaced by the original sheet present at **EP Editor** invocation time. All the means which were temporarily disabled while the "Editor Space" sheet 515 was displayed are now enabled again. Finally control is given back to the initial step 1101 for processing any future **ST Editor** command.

#### E5. RST Editor method

The method for creating or updating RST's used in the preferred embodiment of the present invention is summarized in flowchart 1230 of FIG 12. This method can be seen as the processing of the **RST Editor** command.

- At step 1231, the method is in its default state, waiting for an event to initiate the process.
- At step 1232, the **RST Editor** command is detected, as a result of an user action. This action can be for instance:
  - a specific combination of key on the keyboard 104, or
  - the click of the pointing device 105 on a specific button, or



- any other similar means not further specified here.
  - At step 1233, the parameter of the command is retrieved. It corresponds to a mandatory parameter *RSTE\_name* which can either take a reserved value "NEW" or another value corresponding to a character string name, as found in the "Name" field 2232 of a record 2231 within the RSTMT table 2230. This parameter is recorded as a local variable.
  - At step 1234, some local variables are initialized: the local variable *RSTE\_min* is set to the default value 1 (one), the local variable *RSTE\_max* is set to the default value 16.
  - At step 1235, a test is performed to determine the value taken by the local variable *RSTE\_name*. If found equal to "NEW", then control is given to step 1239; otherwise control is given to step 1236.
  - At step 1236, the RSTT table 2220 is looked up to locate a record 2221 whose "Name" field 2222 is found equal to the value taken by the local variable *RSTE\_name*. If such a record is found, then control is given to step 1238; otherwise control is given to step 1237.
  - At step 1237, an exception handler is invoked to treat this "should not occur" condition. Such operation is implementation dependent and can take different forms such as the display on the display device 106 of an error message pop-up window. Then control is given to the initial step 1231 for processing any future *RST Editor* command.
  - At step 1238,
    - the local variable *RSTE\_min* is set to the value found in the "Min Element #" field 2225 of the record 2221 found at step 1236,
    - the local variable *RSTE\_max* is set to the value found in the "Max Element #" field 2226 of the record 2221 found at step 1236.
- Then the memory location pointed by the "Description Ptr" field 2224 of the record 2221 found at step 1236 (where is recorded the description of the RST according to the RSTDT table 2250 illustrated in FIG 19D) is copied in a working buffer which in turns follows the same RSTDT table 2250.
- This structure is then used to build on the clipboard within the main memory 102 a spreadsheet range of cells illustrating the RST definition copied in the working buffer, each cell successively corresponding to RE or RME names, starting with the first name 2251 up to the last one 2253. Then control is given to step 1240.
- At step 1239, a new name for the newly created RST is determined, according to a name string taking in a preferred embodiment of the present invention the form "New XX" where XX corresponds to a counter value ensuring the name uniqueness with respect to all the names previously defined and recorded in the "Name" fields 702, 712, 722, 2212 and 2222 found in the respective records 701, 711, 721, 2211 and 2221 of the respective tables EFT 700, EPT 710, STT 720, RET 2210 and RSST 2220. Any other similar conventional means could be used instead without departing from the spirit of the invention, as long as the uniqueness of the newly created name is ensured. Then the new name is recorded in the local variable *RSTE\_name*. Then memory space is allocated within the main memory 102 to later record the illustrative range of cells for the new RST. This allocated memory is part of the memory space corresponding to the currently opened electronic spreadsheet file and follows the RSTDT table 2250 illustrated in FIG 19D. Then a new record 2221 is created in the RSTT table 2220, and this new record 2221 is initialized as follows:
    - the "Name" field 2222 is set to the value of the local variable *RSTE\_name* ;
    - the "Last Change Date" field 2223 is set to the system time reference, as known by the central processor 101 ;
    - the "Description Ptr" field 2224 is set to the memory location which has just been allocated ;
    - the "Min Element #" field 2225 is set to the value of the local variable *RSTE\_min*;
    - the "Max Element #" field 2226 is set to the value of the local variable *RSTE\_max* ;

- the "Type" field **2227** is set as follows: the attribute "META" **2228** is set equal to "NO", and the attribute "REFERENCED" **2229** is initialized as follows:
  - The "OWN REFERENCE" (OR) subfield **2229a** is initialized with a prime number not yet assigned to any other OR subfield **709a**, or **719a**, or **729a**, or **780a**, or **2219a**, or **2229a**, or **2240a**. Various conventional techniques can be used for identifying a prime number, and are not further detailed here.
  - The "FILATION REFERENCE" (FR) subfield **2229b** is initialized according to the following formula, where the F set corresponds to the set of RE's and RME constituting the new RST, according to the structure recorded in the "Description Ptr" field **2224**:

$$FR = \prod_{i \in F} OR_i \times LCM(\{FR_i\}_{i \in F})$$

- The "INSTANCE REFERENCE" (IR) subfield **2229c** is initialized with the value 1 (one).
- The "REFERENCED OBJECT" (RO) subfield **2229d** is initialized with the value "NO".
- The "SELECTED CHILDREN" (SC) subfield **2229e** is initialized with the following formula, where the S set corresponds to the set of selected objects (having the "SELECTED" attribute **2242** equal to the value "YES" in the RSTMT table **2230**):

$$SC = \text{"YES"} \text{ if } LCM(\{FR_i\}_{i \in S}) \bmod OR = 0 \text{ \#OR\# } RSTE\_name \in S;$$

$$SC = \text{"No"} \text{ otherwise.}$$

Then a working buffer is allocated in main memory **102** and initialized with a default RST description which corresponds to a RE **2252**. This default RST description is then used to build on the clipboard within the main memory **102** a spreadsheet range of cells illustrating the new RST. This construction is achieved as explained at the end of the step **1238**. Then control is given to step **1240**.

- At step **1240**, the "Editor Space" sheet **615** is made the current sheet and this sheet is turned to write-protect mode while regular row insertion and deletion are disabled. Then the top left cell of the range of cells **614** is selected.

Then the local variable *RE\_name* is filled with the name of the RE corresponding to the row where is located the currently selected cell within the range of cells **614**.

- At step **1241**, the RST Editor Dialog Box **601** is displayed on the display device **106**. The label box **604** is initialized with the value of the local variable *RSTE\_name*.

The text box **606** is filled with the value of the local variable *RSTE\_min*.

The text box **609** is filled with the value of the local variable *RSTE\_max*.

The combo box **610** is filled with the value of the local variable *RE\_name*.

Then the range of cells **614** is updated according to the description recorded in the memory clipboard: the content of the clipboard is pasted on this blank sheet at a fixed cell address **614** (address B2 in a preferred embodiment of the present invention, as shown on FIG 6), so that the user can visualize on the display device **106**, within the window **611** an illustration of the ST.

Then a test is performed to check if all the RE's and RME's contributing to the RST definition illustrated by the range of cells **614**, have the same number of fields. If it is the case, then the two push-buttons "Save" **613** and "Save As" **612** are enabled, so that the click with the pointing device **105** on one of these two push-buttons is recognized as a valid event. Otherwise the two push-buttons "Save" **613** and "Save As" **612** are disabled, so that the click with the pointing device **105** on one of these two push-buttons is not recognized as a valid event.

- At step **1242**, the method is waiting for any user action on the RST Editor Dialog Box **601**. Such user action is typically resulting from a click with the pointing device **105**, but take other similar forms such as, but not limited to a specific combination of key on the keyboard **104**, or any other similar means not further specified here.

- At step **1243**, a user action on the RST Editor Dialog Box **601** is detected.

- If the user action is a click on the push-button "Save" **613**, then control is given to step **1246**;

- if the user action is a click on the push-button "Save As" 612, then control is given to step 1249;
- if the user action is a click on the push-button "Add" 617, then control is given to step 1254;
- 5 ~~• if the user action is a click on the push-button "Delete" 618, then control is given to step 1255;~~
- If the user action is a click on the push-button "Up" 619 or on the push-button "Down" 616, then control is given to step 1256;
- 10 • if the user action is an update of the combo box 610, then control is given to step 1244;
- if the user action is a click on the spin button 607, then control is given to step 1252;
- if the user action is a click on the spin button 608, then control is given to step 1253;
- if the user action is a click on the push-button "Done" 603, or on the closing-window push-button 602, then control is given to step 1258.
- 15 • At step 1244, the ST description is updated in the working buffer by replacing by the RE or RME name found in the combo box 610 the previous RE or RME name corresponding to the RE or RME illustrated by the currently selected cell within the range of cells 614. Then the local variable *RE\_name* is also set equal to the name found in the combo box 610. Then control is given to step 1241.
- 20 • At step 1246, a test is performed to check if the currently edited RST is already referenced by an existing RSTI. For this purpose is considered the value of the "REFERENCED" attribute 2229 within the "Type" field 2227 of the record 2221 within the RSTT table 2220 whose "Name" field 2222 is equal to the local variable *RSTE\_name*. If the value of the "INSTANCE REFERENCE" (IR) subfield 2229c is equal to 1 (one), then control is given to step 1247; otherwise control is given to step 1248.
- 25 • At step 1247, the RSTT table 2220 is updated by refreshing the record 2221 whose "Name" field 2222 is equal to the local variable *RSTE\_name*. For this purpose,
  - the "Last Change Date" field 2223 is set to the system time reference, as known by the central processor 101 ;
  - 30 • the "Min Element #" field 2225 is set to the value of the local variable *RSTE\_min*;
  - the "Max Element #" field 2226 is set to the value of the local variable *RSTE\_max*.
  - The current description of the RST, as illustrated by the range of cells 614, as recorded in the working buffer, and following the RSTDT table 2250 is copied onto the memory location pointed by the "Description Ptr" field 2224.
  - 35 • The "Type" field 2227 is updated as the "FILATION REFERENCE" (FR) subfield 2229b of the "REFERENCED" attribute 2229 is automatically updated thanks to its definition formula depending on the set of RE's, and RME's belonging to the RSTDT table 2250 pointed by the "Description Ptr" field 2224.
  - For each RE name or RME name found in the column 2254 of this RSTDT table 2250, the RET table 2210 is automatically updated within the corresponding record 40 2211 whose "Name" field 2212 matches this RE or RME name, as the subfield "REFERENCED OBJECT" (RO) 2219d (within the "REFERENCED" attribute 2219) is recalculated according to its definition formula.
  - 45 • At step 1248, a warning message notification is issued for informing the user that the edited RST is already instanciated as a RSTI. This can typically be done by displaying on the display device 106 a warning message in a pop-up window, or in a status bar area, but any other similar means could be used instead, without departing from the spirit of the invention. Then the user is prompted to either cancel the current "Save" operation, or to pursue it. This can typically be done by displaying on the display device 50 106 a prompting message in a pop-up window, but any other similar means could be used instead, without departing from the spirit of the invention. Once the user has made his choice through conventional means such as clicking with the pointing device 105 on an "Cancel" or "Continue" push-button present within a prompting message pop-up

window, or any other similar means without departing from the spirit of the invention, control is given to step 1241 if the spreadsheet user decision is to cancel the operation, or to step 1247 if the spreadsheet user decision is to continue the operation.

At step 1249, a test is performed on the value found in the text box 605 to determine if it corresponds to a valid new name. The corresponding criteria are implementation dependent and may take different forms without departing from the spirit of the invention, as long as the new proposed name is a unique character string against all the already defined names recorded in the "Name" fields 702, 712, 722, 2212 and 2222. If validity and uniqueness are proven, then control is given to step 1250; otherwise control is given to step 1251.

At step 1250, memory space is allocated within the main memory 102 to later record the descriptor of the RST. This allocated memory is part of the memory space corresponding to the currently opened electronic spreadsheet file. Then a new record 2221 is created in the RSTT table 2220, and this new record 2221 is initialized as follows:

- the "Name" field 2222 is set to the value found in the text box 605 and validated at step 1249; this field 2222 becoming then the new value of the *RSTE\_name* local variable;
- the "Last Change Date" field 2223 is set to the system time reference, as known by the central processor 101 ;
- the "Description Ptr" field 2224 is set to the memory location which has just been allocated ;
- the "Min Element #" field 2225 is set to the value of the local variable *RSTE\_min*;
- the "Max Element #" field 2226 is set to the value of the local variable *RSTE\_max* ; and
- the "Type" field 2227 is set as follows: the attribute "META" 2228 is set equal to "NO", and the attribute "REFERENCED" 2229 is initialized as follows:
  - The "OWN REFERENCE" (OR) subfield 2229a is initialized with a prime number not yet assigned to any other OR subfield 709a, or 719a, or 729a, or 780a, or 2219a, or 2229a, or 2240a. Various conventional techniques can be used for identifying a prime number, and are not further detailed here.
  - The "FILATION REFERENCE" (FR) subfield 2229b is initialized according to the following formula, where the F set corresponds to the set of RE's and RME constituting the new RST, according to the structure recorded in the "Description Ptr" field 2224:

$$FR = \prod_{i \in F} OR_i \times LCM(\{FR_i\}_{i \in F})$$

- The "INSTANCE REFERENCE" (IR) subfield 2229c is initialized with the value 1 (one).
- The "REFERENCED OBJECT" (RO) subfield 2229d is initialized with the value "NO".
- The "SELECTED CHILDREN" (SC) subfield 2229e is initialized with the following formula, where the S set corresponds to the set of selected objects (having the "SELECTED" attribute 2242 equal to the value "YES" in the RSTMT table 2230):

$$SC = \text{"YES"} \text{ if } LCM(\{FR_i\}_{i \in S}) \bmod OR = 0 \text{ \#OR\# } RSTE\_name \in S;$$

$$SC = \text{"No"} \text{ otherwise.}$$

- The current description of the RST, as illustrated by the range of cells 614, as recorded in the working buffer, and following the RSTDT table 2250 is copied onto the memory location pointed by the "Description Ptr" field 2224.
- For each RE name or RME name found in the column 2254 of this RSTDT table 2250, the RET table 2210 is automatically updated within the corresponding record 2211 whose "Name" field 2212 matches this RE or RME name, as the subfield "REFERENCED OBJECT" (RO) 2229d (within the "REFERENCED" attribute 2219) is recalculated according to its definition formula.

At step 1251, a warning message notification is issued for informing the user that a valid and unique name must be specified in the text box 605 prior to clicking on the "Save As"

push-button 612. This can typically be done by displaying on the display device 106 a warning message in a pop-up window, or in a status bar area, but any other similar means could be used instead, without departing from the spirit of the invention. Once the user has acknowledged this notification message through conventional means such as clicking with the pointing device 105 on an "OK" push-button present within a warning message pop-up window, or any other similar means without departing from the spirit of the invention, control is given to step 1241.

- At step 1252, the local variable *RSTE\_min* is either incremented or decremented by 1 (one) according to the direction (up or down) specified by the pointing device 105 on the spin button 607, and as long as its value remains positive and less than or equal to both an upper limit set equal to 254 in a preferred embodiment of the present invention and to the value shown in the text box 609. Then control is given to step 1241.
- At step 1253, the local variable *RSTE\_max* is either incremented or decremented by 1 (one) according to the direction (up or down) specified by the pointing device 105 on the spin button 608, and as long as its value remains positive, greater than the value shown in the text box 606 and less than or equal to an upper limit set equal to 254 in a preferred embodiment of the present invention. Then control is given to step 1241.
- At step 1254, a new row is inserted in the range of cells 614 illustrating the edited RST, above the row where the last selected cell was previously located. Then the left most cell located on the new row within the range of cells 614 is selected. Then the RST definition is updated in the working buffer by introducing a new RME which is identified, like the other ones, by a name, which is also assigned to the local variable *RE\_name*. In addition the current description of the RST, as illustrated by the range of cells 614, as recorded in the working buffer, and following the RSTDT table 2250 is copied onto the memory location pointed by the "Description Ptr" field 2224. Then control is given to step 1241.
- At step 1255, the row containing the selected cell is removed from the range of cells 614, so that the next RE or meta-element gets selected. Then the RST definition is updated by removing the deleted RME which was identified by its name. In addition the current description of the RST, as illustrated by the range of cells 614, as recorded in the working buffer, and following the RSTDT table 2250 is copied onto the memory location pointed by the "Description Ptr" field 2224. Then control is given to step 1257.
- At step 1256, the current cell within the "Editor Space" sheet 615 is respectively moved up or down if the spreadsheet user has clicked with the pointing device 105 on the "Up" push-button 619, or on the "Down" push-button 616, and also if this movement does not move the current cell away from the range of cells 614 illustrating the RST.
- At step 1257, the local variable *RE\_name* is set equal to the name of the RE or RME corresponding to either the RE or the RME identified by the currently selected cell within the range of cells 614. Then control is given to step 1241.
- At step 1258, the RST Editor Dialog Box 601 is closed so that it disappears from the display device 106, then the "Editor Space" sheet 615 is removed from the display window so that it is replaced by the original sheet present at *RST Editor* invocation time. All the means which were temporarily disabled while the "Editor Space" sheet 615 was displayed are now enabled again. Finally control is given back to the initial step 1231 for processing any future *RST Editor* command.

#### E6. ST Instanciator method

The method for creating a STI abiding by a defined ST used in the preferred embodiment of the present invention is summarized in flowchart 1400 of FIG 14A and FIG 14B, where the later corresponds to the *CreateSTI* routine. This method can be seen as the processing of the *ST Instanciator* command.

- At step 1401, the method is in its default state, waiting for an event to initiate the process.

- At step 1402, the *ST Instanciator* command is detected, as a result of a user action. This action can be for instance a specific combination of key on the keyboard 104, or the click of the pointing device 105 on a specific button, or any other similar means not further specified here.
- 5 • At step 1403, a test is performed to check if the currently selected cell is contained within a sheet where a RSTI is present. This test can be done by parsing the RSTIT table 2260 to identify any record 2261 whose *Address* field 2262 corresponds to the same sheet as the currently selected cell. If it is the case, then control is given to step 1404 ; otherwise control is given to step 1405.
- 10 • At step 1404, a warning message notification is issued for informing the user that a STI cannot be individually created on a sheet where a RSTI already exists. This can typically be done by displaying on the display device 106 a warning message in a pop-up window, or in a status bar area, but any other similar means could be used instead, without departing from the spirit of the invention. Once the user has acknowledged this notification message through conventional means such as clicking with the pointing device 105 on an "OK" push-button present within a warning message pop-up window, or any other similar means without departing from the spirit of the invention, control is given to step 1401.
- 15 • At step 1405, the command parameter *ST\_name* is first retrieved: it corresponds to the name of the ST that the STI to be created will abide by. This parameter *ST\_name* is used to parse the STT table 720 in order to find the record 721 whose "Name" field 722 matches the parameter *ST\_name*. Once this record 721 is found, its fields "Min Element #" 725 and "Max Element #" 726 are respectively memorized as local variables *STI\_min* and *STI\_max*. Then its field "Description Ptr" 724 is used to determine, according to the referenced STDT table 760, the number of meta-elements defined within the ST, and the number of cells defined within each element or meta-element member of the ST. The first number is memorized in a local variable *STI\_meta*, and the second number is memorized in a local variable *STI\_width* 1325 (representing the number of columns of the future STI).
- 20 Then another local variable *STI\_element* is initialized with the value taken by *STI\_min*. Then another local variable *STI\_critical* is initialized with the default value "yes". Then another local variable *STI\_sheet\_width* 1321 is initialized with the total number of columns in the current sheet 1320.
- 25 Then another local variable *STI\_sheet\_height* 1322 is initialized with the total number of rows in the current sheet 1320.
- 30 Then another local variable *STI\_mode* is initialized with the value OVERLAY.
- 35 • At step 1406, some other local variables are first built or updated. The position of the currently selected cell 1327 is first represented by the local variables *STI\_offset\_width* 1323 and *STI\_offset\_height* 1324 corresponding respectively to the number of columns and of rows between the top left cell of the current sheet 1320 and the currently selected cell 1327.
- 40 Then the number of rows of the future STI is represented by the local variable *STI\_height* 1326, computed as the sum of the local variables *STI\_meta* and *STI\_element*.
- 45 Second some working ranges of cells are determined through the evaluation of their addresses.
- 50 The range of cells *STI\_range* 1328 corresponding to the future STI is first determined as the range of cells with the currently selected cell 1327 as the top left cell, and with a number of rows and columns respectively equal to *STI\_height* 1326 and *STI\_width* 1325.
- Then the range of cells *STI\_horizontal\_flushed\_range* 1330 is determined as the range of cells sharing the same rows as *STI\_range* 1328, and occupying the *STI\_width* 1325 rightmost columns of the current sheet 1320.



Then the range of cells *STI\_horizontal\_kept\_range* 1329 is determined as the range of cells sharing the same rows as *STI\_range* 1328, and occupying the columns located between those of *STI\_range* 1328 and *STI\_horizontal\_flushed\_range* 1330.

Then the range of cells *STI\_vertical\_flushed\_range* 1332 is determined as the range of cells sharing the same columns as *STI\_range* 1328, and occupying the *STI\_height* 1326 bottom columns of the current sheet 1320.

Then the range of cells *STI\_vertical\_kept\_range* 1331 is determined as the range of cells sharing the same columns as *STI\_range* 1328, and occupying the rows located between those of *STI\_range* 1328 and *STI\_vertical\_flushed\_range* 1332.

10 • At step 1407, two sums are performed to check if the future STI will fit within the boundaries of the current sheet 1320.

- If the sum of the local variables *STI\_offset\_width* 1323 and *STI\_width* 1325 is found greater than the local variable *STI\_sheet\_width* 1321, then a local variable *STI\_too\_wide* is set to "YES"; otherwise it is set to "NO".

15 • If the sum of the local variables *STI\_offset\_height* 1324 and *STI\_height* 1326 is found greater than the local variable *STI\_sheet\_height* 1322, then a local variable *STI\_too\_high* is set to "YES"; otherwise it is set to "NO".

20 • At step 1408, several tests are performed to evaluate the potential impact of the creation of the future STI, according to the five possible instantiation modes, on any already existing STI or data. These tests require to parse the STIT table 750, and to visit each record 751 to learn the address ("Address" field 752) and the importance ("Critical" field 755) of every already defined STI. These tests evaluate either if two given ranges of cells partially overlap (meaning that there exist in the first range of cells at least one cell belonging to the second range of cells and at least one cell not belonging to the second range of cells) or if a first given range of cells is included within a second given range of cells (meaning that every cell belonging to the first range of cells belongs too to the second range of cells). Different conventional range comparison techniques can be used for evaluating either range partial overlapping or range inclusion, without departing from the spirit of the present invention; they will not be described in the preferred embodiment of the present invention.

30 First the OVERLAY mode of instantiation is investigated.

- If there exists at least one existing STI whose "Critical" field 755 takes the value "YES" and which partially overlaps the range of cells *STI\_range* 1328, then the local test variable *STI\_overlay\_critical* takes the value "YES"; otherwise the local test variable *STI\_overlay\_critical* takes the value "NO".

- If there exists at least one existing STI whose "Critical" field 755 takes the value "NO" and which partially overlaps the range of cells *STI\_range* 1328, then the local test variable *STI\_overlay\_other* takes the value "YES"; otherwise the local test variable *STI\_overlay\_other* takes the value "NO".

- If all the cells within the range of cells *STI\_range* 1328 are empty (containing none data), then the local test variable *STI\_overlay\_data* takes the value "NO"; otherwise the local test variable *STI\_overlay\_data* takes the value "YES".

Second the HORIZONTAL\_INSERT mode of instantiation is investigated.

- If there exists at least one existing STI whose "Critical" field 755 takes the value "YES" and which partially overlaps the range of cells made of the entire row where is located the currently selected cell 1327, or which partially overlaps the range of cells constituted by the last bottom *STI\_height* 1326 rows, or which is included in the range of cells constituted by the last bottom *STI\_height* 1326 rows, then the local test variable *STI\_horizontal\_critical* takes the value "YES"; otherwise the local test variable *STI\_horizontal\_critical* takes the value "NO".

- If there exists at least one existing STI whose "Critical" field 755 takes the value "NO" and which partially overlaps the range of cells made of the entire row where is located the currently selected cell 1327, or which partially overlaps the range of cells

constituted by the last bottom *STI\_height* 1326 rows, or which is included in the range of cells constituted by the last bottom *STI\_height* 1326 rows, then the local test variable *STI\_horizontal\_other* takes the value "YES"; otherwise the local test variable *STI\_horizontal\_other* takes the value "NO".

- 5 • If all the cells within the range of cells constituted by the last bottom *STI\_height* 1326 rows are empty (containing none data), then the local test variable *STI\_horizontal\_data* takes the value "NO"; otherwise the local test variable *STI\_horizontal\_data* takes the value "YES".

Third the HORIZONTAL\_INSERT\_BY\_RANGE mode of instantiation is investigated.

- 10 • If there exists at least one existing STI whose "*Critical*" field 755 takes the value "YES" and which partially overlaps the range of cells constituted by the concatenation of the two ranges of cells *STI\_range* 1328 and *STI\_vertical\_kept\_range* 1331, or which partially overlaps the range of cells *STI\_vertical\_flushed\_range* 1332, or which is included in the range of cells *STI\_vertical\_flushed\_range* 1332, then the local test variable *STI\_horizontal\_range\_critical* takes the value "YES"; otherwise the local test variable *STI\_horizontal\_range\_critical* takes the value "NO".
- 15 • If there exists at least one existing STI whose "*Critical*" field 755 takes the value "NO" and which partially overlaps the range of cells constituted by the concatenation of the two ranges of cells *STI\_range* 1328 and *STI\_vertical\_kept\_range* 1331, or which partially overlaps the range of cells *STI\_vertical\_flushed\_range* 1332, or which is included in the range of cells *STI\_vertical\_flushed\_range* 1332, then the local test variable *STI\_horizontal\_range\_other* takes the value "YES"; otherwise the local test variable *STI\_horizontal\_range\_other* takes the value "NO".
- 20 • If all the cells within the range of cells *STI\_vertical\_flushed\_range* 1332 are empty (containing none data), then the local test variable *STI\_horizontal\_range\_data* takes the value "NO"; otherwise the local test variable *STI\_horizontal\_range\_data* takes the value "YES".
- 25 • If all the cells within the range of cells *STI\_vertical\_flushed\_range* 1332 are empty (containing none data), then the local test variable *STI\_horizontal\_range\_data* takes the value "NO"; otherwise the local test variable *STI\_horizontal\_range\_data* takes the value "YES".

Fourth the VERTICAL\_INSERT mode of instantiation is investigated.

- 30 • If there exists at least one existing STI whose "*Critical*" field 755 takes the value "YES" and which partially overlaps the range of cells made of the entire column where is located the currently selected cell 1327, or which partially overlaps the range of cells constituted by the last right *STI\_width* 1325 columns, or which is included in the range of cells constituted by the last right *STI\_width* 1325 columns, then the local test variable *STI\_vertical\_critical* takes the value "YES"; otherwise the local test variable *STI\_vertical\_critical* takes the value "NO".
- 35 • If there exists at least one existing STI whose "*Critical*" field 755 takes the value "NO" and which partially overlaps the range of cells made of the entire column where is located the currently selected cell 1327, or which partially overlaps the range of cells constituted by the last right *STI\_width* 1325 columns, or which is included in the range of cells constituted by the last right *STI\_width* 1325 columns, then the local test variable *STI\_vertical\_other* takes the value "YES"; otherwise the local test variable *STI\_vertical\_other* takes the value "NO".
- 40 • If all the cells within the range of cells constituted by the last right *STI\_width* 1325 columns are empty (containing no data), then the local test variable *STI\_vertical\_data* takes the value "NO"; otherwise the local test variable *STI\_vertical\_data* takes the value "YES".
- 45 • If all the cells within the range of cells constituted by the last right *STI\_width* 1325 columns are empty (containing no data), then the local test variable *STI\_vertical\_data* takes the value "NO"; otherwise the local test variable *STI\_vertical\_data* takes the value "YES".

Fifth the VERTICAL\_INSERT\_BY\_RANGE mode of instantiation is investigated.

- 50 • If there exists at least one existing STI whose "*Critical*" field 755 takes the value "YES" and which partially overlaps the range of cells constituted by the concatenation of the two ranges of cells *STI\_range* 1328 and *STI\_horizontal\_kept\_range* 1329, or which partially overlaps the range of cells *STI\_horizontal\_flushed\_range* 1330, or which is included in the range of cells *STI\_horizontal\_flushed\_range* 1330, then the local test

variable *STI\_vertical\_range\_critical* takes the value "yes"; otherwise the local test variable *STI\_vertical\_range\_critical* takes the value "no".

- If there exists at least one existing STI whose "Critical" field 755 takes the value "no" and which partially overlaps the range of cells constituted by the concatenation of the two ranges of cells *STI\_range\_1328* and *STI\_horizontal\_kept\_range\_1329*, or which partially overlaps the range of cells *STI\_horizontal\_flushed\_range\_1330*, or which is included in the range of cells *STI\_horizontal\_flushed\_range\_1330*, then the local test variable *STI\_vertical\_range\_other* takes the value "yes"; otherwise the local test variable *STI\_vertical\_range\_other* takes the value "no".
- If all the cells within the range of cells *STI\_horizontal\_flushed\_range\_1330* are empty (containing none data), then the local test variable *STI\_vertical\_range\_data* takes the value "no"; otherwise the local test variable *STI\_vertical\_range\_data* takes the value "yes".
- At step 1409, the ST Instanciator Dialog Box 1300 is displayed on the display device 106. The "Critical" check box 1314 displays a check mark if the local variable *STI\_critical* takes the value "yes"; otherwise (value "no"), the "Critical" check box 1314 is kept with a blank empty display. The label box 1315 is initialized with the value of the local variable *ST\_name*. The text box 1312 is filled with the value of the local variable *STI\_element*. The label box 1311 is filled with the value of the local variable *STI\_too\_wide* and the label box 1310 is filled with the value of the local variable *STI\_too\_high*. The 15 label boxes 1304 are filled row after row, starting with the top row, from the left to the right, with the values of the following local variables in the following order: *STI\_overlay\_critical*, *STI\_overlay\_other*, *STI\_overlay\_data*, *STI\_horizontal\_critical*, *STI\_horizontal\_other*, *STI\_horizontal\_data*, *STI\_horizontal\_range\_critical*, *STI\_horizontal\_range\_other*, *STI\_horizontal\_range\_data*, *STI\_vertical\_critical*, *STI\_vertical\_other*, *STI\_vertical\_data*, *STI\_vertical\_range\_critical*, *STI\_vertical\_range\_other*, *STI\_vertical\_range\_data*. Then if the local variable *STI\_mode* takes the respective value OVERLAY, or HORIZONTAL\_INSERT, or HORIZONTAL\_INSERT\_BY\_RANGE, or VERTICAL\_INSERT, or VERTICAL\_INSERT\_BY\_RANGE, then the option button "Overlay" 1309, or "Horizontal Insert" 1308, or "Horizontal Insert by Range" 1307, or "Vertical Insert" 1306, or "Vertical Insert by Range" 1305 displays alone a black point. Finally the "Create" push-button 1303 is disabled as soon as one of the following local variables takes the value "yes": *STI\_too\_wide*, *STI\_too\_high*, *STI\_overlay\_critical* (only taken into account if the local variable *STI\_mode* is equal to OVERLAY), *STI\_horizontal\_critical* (only taken into account if the local variable *STI\_mode* is equal to HORIZONTAL\_INSERT), *STI\_vertical\_critical* (only taken into account if the local variable *STI\_mode* is equal to VERTICAL\_INSERT), *STI\_horizontal\_range\_critical* (only taken into account if the local variable *STI\_mode* is equal to HORIZONTAL\_INSERT\_BY\_RANGE), *STI\_vertical\_range\_critical* (only taken into account if the local variable *STI\_mode* is equal to VERTICAL\_INSERT\_BY\_RANGE); otherwise the "Create" push-button 1303 is enabled.
- At step 1410, the method is waiting for any user action on the ST Instanciator Dialog Box 1300, or on any change of the currently selected cell. Such user action is typically resulting from a click with the pointing device 105, but take other similar forms such as, but not limited to a specific combination of key on the keyboard 104, or any other similar means not further specified here.
- At step 1411, a user action on the ST Instanciator Dialog Box 1300, or a change of the currently selected cell is detected.
  - If the user action is a click on the "Create" push-button 1303, then control is given to step 1416;
  - if the user action is a click on the upper part of the spin button 1313, then control is given to step 1415;
  - if the user action is a click on the lower part of the spin button 1313, then control is given to step 1414;

- if the user action is a click on the "*Critical*" check box 1314, then control is given to step 1413;
  - if the user action is a click on one of the option buttons 1309, or 1308, or 1307, or 1306, or 1305, then control is given to step 1412;
  - 5 • if the user action is a click on the "*Cancel*" push-button 1302, or on the closing-window push-button 1301, then control is given to step 1418;
  - finally if the user action is a change in the position of the currently selected cell, then control is given to step 1406.
  - 10 • At step 1412, the local variable *STI\_mode* takes the value OVERLAY, OR HORIZONTAL\_INSERT, OR HORIZONTAL\_INSERT\_BY\_RANGE, OR VERTICAL\_INSERT, OR VERTICAL\_INSERT\_BY\_RANGE if the spreadsheet user has respectively clicked with the pointing device 105 on the option button 1309, or 1308, or 1307, or 1306, or 1305. Then control is given to step 1406.
  - At step 1413, the local variable *STI\_critical* is updated in order to swap between the values "YES" and "NO". Then control is given to step 1406.
  - 15 • At step 1414, the local variable *STI\_element* is decremented by 1 (one), as long as its value remains greater than or equal to the value of the local variable *STI\_min*. Then control is given to step 1406.
  - At step 1415, the local variable *STI\_element* is incremented by 1 (one), as long as its value remains less than or equal to the value of the local variable *STI\_max*. Then control is given to step 1406.
  - 20 • At step 1416, the STIT table 750 is visited to remove from it every record 751 corresponding to a STI corrupted by the introduction of the new instance, as identified during the step 1408 for the insertion mode represented by the local variable *STI\_mode*.
  - 25 Then the STT table 720 is updated to reflect the removal of each STI. For each removed STI, the INSTANCE REFERENCE (IR) field 729c of the "REFERENCED" attribute 729 of the record 721 whose "Name" field 722 is equal to the "ST" field 753 of the record 751 of the STIT table 750 corresponding to the removed STI, is divided by 2 (two).
  - At step 1417, the routine CreateSTI is called.
  - 30 • At step 1418, the ST Instanciator Dialog Box 1300 is closed so that it disappears from the display device 106. Finally control is given back to the initial step 1401 for processing any future *ST Instanciator* command.
- The following steps, all part of FIG 14B, correspond to the execution of the *CreateSTI* routine, as used in the preferred embodiment of the present invention
- 35 • At step 1419, a new record 751 is introduced in the STIT table 750. Within this record 751, the "Address" field 752 is initialized with the address of the range of cells *STI\_range* 1328, the "ST" field 753 is initialized with the value of the local variable *ST\_name*, the "Element #" field 754 is initialized with the value of the local variable *STI\_element*, the "Critical" field 755 is initialized with the value of the local variable *STI\_critical*, the
  - 40 "Header Size" field 756 is initialized with the number of meta-elements constituting the header part of the new STI (this number being equal to the number of pairs in the header part 767 of the STDT table 760 associated to the ST that the new STI will abide by), and the "Footer Size" field 757 is initialized with the number of meta-elements constituting the footer part of the new STI (this number being equal to the number of
  - 45 pairs in the footer part 766 of the STDT table 760 associated to the ST abided by the new STI). Then the STT table 720 is scanned to identify the record 721 whose "Name" field is found equal to the local variable *ST\_name*. Once found, the "REFERENCED" attribute 729 within the "Type" field 727 of this record 721 is updated by multiplying the "INSTANCE REFERENCE" subfield 729c by 2 (two).
  - 50 • At step 1420 a test is performed to check the value of the local variable *STI\_mode*.
    - If this value is found equal to OVERLAY then control is given to step 1425,
    - If this value is found equal to HORIZONTAL\_INSERT then control is given to step 1424,

- If this value is found equal to `HORIZONTAL_INSERT_BY_RANGE` then control is given to step 1422,
  - If this value is found equal to `VERTICAL_INSERT` then control is given to step 1423,
  - If this value is found equal to `VERTICAL_INSERT_BY_RANGE` then control is given to step 1421.
- 5
- At step 1421, the range of cells *STI\_range* 1328 is selected to become the currently selected range of cells, with the currently selected cell being kept in its former position 1327 and then a regular operation of "column insertion within selected range" is performed. Then control is given to step 1425.
- 10
- At step 1422, the range of cells *STI\_range* 1328 is selected to become the currently selected range of cells, with the currently selected cell being kept in its former position 1327 and then a regular operation of "row insertion within selected range" is performed. Then control is given to step 1425.
- 15
- At step 1423, the range of cells *STI\_range* 1328 is selected to become the currently selected range of cells, with the currently selected cell being kept in its former position 1327 and then a regular operation of "column insertion" is performed. Then control is given to step 1425.
- 20
- At step 1424, the range of cells *STI\_range* 1328 is selected to become the currently selected range of cells, with the currently selected cell being kept in its former position 1327 and then a regular operation of "row insertion" is performed. Then control is given to step 1425.
- 25
- At step 1425, a local variable *STI\_index* is initialized to the value taken by the local variable *STI\_element*. Then the STT table 720 is parsed to identify the record 721 whose "Name" field 722 matches the value of the local variable *ST\_name*. Within this record 721 is retrieved the "Description Ptr" field 724 allowing to locate in memory the STDT table 760 associated to the ST that the new STI to be created will abide by. Then the first pair 761 of element or MEF name and element or MEP name found within this STDT table 760 is set as the current pair of names: (EF or MEF name, EP or MEP name).
- 30
- At step 1426, the EPT table 710 is parsed to find the record 711 whose "Name" field 712 is found equal to the EP or MEP name within the current pair. Once this record 711 is found, its "Description Ptr" field 714 is retrieved to locate in memory the range of cells illustrating the EP or MEP. This description of the EP or MEP is copy-pasted by value only onto the currently selected cell, so that the corresponding row within the *STI\_range* receives the EP or MEP initial values. Then the EFT table 700 is parsed to find the record 701 whose "Name" field 702 is found equal to the EF or MEF name within the current pair. Once this record 701 is found, its "Description Ptr" field 704 is retrieved to locate in memory the range of cells illustrating the EF or MEF. This description of the EF or MEF is copy-pasted by attribute only onto the currently selected cell, so that the corresponding row within the *STI\_range* receives the EF or MEF attributes.
- 35
- At step 1427 a test is performed to check if the current pair (EF or MEF name, EP or MEP name) corresponds to an element or to a meta-element. In the first case, control is given to step 1428, and in the second case control is given to step 1429.
- 40
- At step 1428, the local variable *STI\_index* is decremented by 1 (one). Then control is given to step 1430.
- 45
- At step 1429, a test is performed to check if the current pair (EF or MEF name, EP or MEP name) is the last one 763 within the STDT table 760. If it is the case, the execution of the **CreateSTI** routine completes by returning control to the routine caller, otherwise control is given to step 1431.
- 50
- At step 1430, a test is performed to check if the local variable *STI\_index* is equal to 0 (zero). If it is the case, then control is given to step 1429, otherwise control is given to step 1432.

- At step 1431, the pair of names (EF or MEF name, EP or MEP name) following the current one in the STDT table 760 becomes the current pair of names.
- At step 1432, the currently selected cell is moved downwards by one row. Then control is given to step 1426.

#### 5 E7. STI Deletion Manager method

The method for deleting within a STI either the content of selected cells, or selected elements or even the whole STI used in the preferred embodiment of the present invention is summarized in flowchart 1800 of FIG 15A. This method can be seen as the processing of the **STI Deletion Manager** command.

- 10 • At step 1801, the method is in its default state, waiting for an event to initiate the process.
- At step 1802, the **STI Deletion Manager** command is detected, as a result of a user action. This action can be for instance a specific combination of key on the keyboard 104, or the click of the pointing device 105 on a specific button, or any other similar means not further specified here.

15 When the **STI Deletion Manager** command is detected, the current spreadsheet selection corresponds to a range of cells, possibly reduced to a single individual cell, which is known as the currently selected range of cells and which comprises the currently selected cell. If this currently selected cell is not the top left cell within the currently selected range of cells, then the top left cell of the currently selected range of cells becomes the currently selected cell.

- 20 • At step 1803, a test is performed to check if the currently selected cell is located within an existing STI. This test is performed by parsing the STIT table 750 and visiting in each record 751 the "Address" field 752 to determine if the range of cells address specified in this field does include the address of the individual currently selected cell. If it is the case, then the currently selected cell is contained in a STI named *STDM\_instance\_range* and control is given to step 1804 ; otherwise control is given to step 1811.

- 30 • At step 1804, the record 751 found at the step 1803 is first retrieved to initialize local variables from its fields describing the STI *STDM\_instance\_range* to which belongs the currently selected cell: the local variable *ST\_name* is initialized with the value of the field "ST" 753; the local variable *STDM\_element* is initialized with the value of the "Element #" field 754; the local variable *STDM\_critical* is initialized with the value of the "Critical" field 755; the local variable *STDM\_header\_size* is initialized with the value of the "Header Size" field 756; the local variable *STDM\_footer\_size* is initialized with the value of the "Footer Size" field 757. Then the local variable *ST\_name* is used to parse the STT table 720 in order to find the record 721 whose "Name" field 722 matches the parameter *ST\_name*. Once this record 721 is found, its field "Min Element #" 725 is memorized as the local variable *STDM\_min*. Then another local variable *STDM\_mode* is initialized with the value DELETE\_IN\_FIELDS\_IN\_SELECTED\_RANGE. Then the position of the currently selected cell is used to initialize the local variable *STDM\_offset\_height* corresponding to the number of rows between the top left cell of the range of cells *STDM\_instance\_range* and the currently selected cell. Then the number of rows of the currently selected range of cells *STDM\_range* is represented by the local variable *STDM\_height*.

- 45 • At step 1805, a series of tests is performed to determine the relative position of the currently selected range of cells with respect to the current STI *STDM\_instance\_range*. First a local variable *STDM\_header\_overlap* takes the value 1 (one) if the value of the local variable *STDM\_offset\_height* is less than the value of the local variable *STDM\_header\_size*; otherwise the local variable *STDM\_header\_overlap* takes the value 0 (zero). Then a local variable *STDM\_footer\_overlap* takes the value 1 (one) if the sum of the values of the local variables *STDM\_offset\_height* and *STDM\_height* is found greater than the sum of the values of the local variables *STDM\_header\_size* and *STDM\_element*. Then a local variable *STDM\_body\_overlap* takes the value of the



formula:  $STDM\_header\_overlap \times STDM\_data1 + (1 - STDM\_header\_overlap) \times STDM\_data2$ , where  $STDM\_data1$  takes the value 1 (respectively 0) if the sum of the values of the local variables  $STDM\_offset\_height$  and  $STDM\_height$  is found greater than (respectively less than or equal to) the value of the local variable  $STDM\_header\_size$ ; and where  $STDM\_data2$  takes the value 1 (respectively 0) if the value of the local variable  $STDM\_offset\_height$  is found less than (respectively greater than or equal to) the sum of the values of the local variables  $STDM\_header\_size$  and  $STDM\_element$ .

- At step 1806, the number of deleted elements is evaluated to then verify that the remaining number of elements will not be too small, that is below the lower limit  $STDM\_min$ . This number of deleted elements is recorded in the local variable  $STDM\_delete\_element\_#$  whose value is given by the following formula:  
 $STDM\_body\_overlap \times (STDM\_height - STDM\_header\_overlap \times (STDM\_header\_size - STDM\_offset\_height)) - STDM\_footer\_overlap \times (STDM\_offset\_height + STDM\_height - STDM\_header\_size - STDM\_element)$ .
- At step 1807, a first local variable  $STDM\_too\_small$  is set to the value "YES" if the sum of the values of the local variables  $STDM\_deleted\_element\_#$  and  $STDM\_min$  is found greater than the value of the local variable  $STDM\_element$ ; otherwise this local variable  $STDM\_too\_small$  takes the value "NO". Then a second local variable  $STDM\_outside\_body$  is set to the value "NO" if both the local variables  $STDM\_header\_overlap$  and  $STDM\_footer\_overlap$  take the value 0 (zero); otherwise this local variable  $STDM\_outside\_body$  is set to the value "YES".
- At step 1808, the ST Delete Manager Dialog Box 1900 is displayed on the display device 106. The "Critical" check box 1910 displays a check mark if the local variable  $STDM\_critical$  takes the value "YES"; otherwise (value "NO"), the "Critical" check box 1910 is kept with a blank empty display. The label box 1911 is initialized with the value of the local variable  $ST\_name$ . The text box 1908 is filled with the value of the local variable  $STDM\_height$ . The label box 1907 is filled with the value of the local variable  $STDM\_too\_small$ , and the label box 1904 is filled with the value of the local variable  $STDM\_outside\_body$ . Then if the local variable  $STDM\_mode$  takes the respective value
  - DELETE\_IN\_FIELDS\_IN\_SELECTED\_RANGE, or
  - DELETE\_IN\_FIELDS\_IN\_SELECTED\_ROWS, or
  - DELETE\_SELECTED\_ELEMENTS, or
  - DELETE\_SELECTED\_INSTANCE,
 then the option button 1905, or 1906, or 1912, or 1913 displays alone a black point. Finally the "Delete" push-button 1903 is disabled as soon as one of the following local variables takes the value "YES":  $STDM\_too\_high$ ,  $STDM\_outside\_body$ , when the local variable  $STDM\_mode$  is equal to DELETE\_SELECTED\_ELEMENTS; otherwise the "Delete" push-button 1903 is enabled.
- At step 1809, the method is waiting for any user action on the ST Delete Manager Dialog Box 1900. Such user action is typically resulting from a click with the pointing device 105, but take other similar forms such as, but not limited to a specific combination of key on the keyboard 104, or any other similar means not further specified here.
- At step 1810, a user action on the ST Delete Manager Dialog Box 1900 is detected.
  - If the user action is a click on the "Delete" push-button 1903, then control is given to step 1824;
  - if the user action is a click on the upper part of the spin button 1909, then control is given to step 1821;
  - if the user action is a click on the lower part of the spin button 1909, then control is given to step 1820;
  - if the user action is a click on the "Critical" check box 1910, then control is given to step 1822;

- if the user action is a click on one of the option buttons **1906**, or **1905**, or **1912**, or **1913**, then control is given to step **1823**;
  - if the user action is a click on the "Cancel" push-button **1902**, or on the closing-window push-button **1901**, then control is given to step **1830**.
- 5 • At step **1811**, the local variable *STDM\_mode* is initialized with the value *CONTENT\_DELETE*. Then the number of rows and of columns of the currently selected range of cells *STDM\_range* is represented respectively by the local variables *STDM\_height* and *STDM\_width*. Then the range of cells *STDM\_right\_range* is determined as the range of cells sharing the same rows as *STDM\_range*, and occupying the columns located on the
- 10 right of the range of cells *STDM\_range*. Then the range of cells *STDM\_bottom\_range* is determined as the range of cells sharing the same columns as *STDM\_range*, and occupying the rows located below those of *STDM\_range*. Then the range of cells *STDM\_left\_range* is determined as the range of cells sharing the same rows as *STDM\_range*, and occupying the columns located on the left of the range of cells
- 15 *STDM\_range*. Then the range of cells *STDM\_top\_range* is determined as the range of cells sharing the same columns as *STDM\_range*, and occupying the rows located above those of *STDM\_range*.
- At step **1812**, several tests are performed to evaluate the potential impact of the deletion, according to four possible deletion modes, on any already existing STI or data. These tests require to parse the STIT table **750**, and to visit each record **751** to learn the address ("Address" field **752**) and the importance ("Critical" field **755**) of every already defined STI. These tests evaluate either if two given ranges of cells partially overlap (meaning that there exist in the first range of cells at least one cell belonging to the
- 20 second range of cells and at least one cell not belonging to the second range of cells) or if a first given range of cells is included within a second given range of cells (meaning that every cell belonging to the first range of cells also belongs to the second range of cells). Different conventional range comparison techniques can be used for evaluating either range partial overlapping or range inclusion, without departing from the spirit of the present invention; they will not be described in the preferred embodiment of the
- 25 present invention.
- 30 First the *HORIZONTAL\_DELETE* mode of deletion is investigated.
- If there exists at least one existing STI whose "Critical" field **755** takes the value "YES" and which partially overlaps the range of cells made of the entire rows where is located the currently selected range of cells *STDM\_range*, or which is included in the
- 35 range of cells made of the entire rows where is located the currently selected range of cells *STDM\_range*, then the local test variable *STDM\_horizontal\_critical* takes the value "YES"; otherwise the local test variable *STDM\_horizontal\_critical* takes the value "NO".
- If there exists at least one existing STI whose "Critical" field **755** takes the value "NO" and which partially overlaps the range of cells made of the entire rows where is located the currently selected range of cells *STDM\_range*, or which is included in the
- 40 range of cells made of the entire rows where is located the currently selected range of cells *STDM\_range*, then the local test variable *STDM\_horizontal\_other* takes the value "YES"; otherwise the local test variable *STDM\_horizontal\_other* takes the value "NO".
- 45
- If all the cells within the range of cells made of the entire rows where is located the currently selected range of cells *STDM\_range* are empty (containing none data), then the local test variable *STDM\_horizontal\_data* takes the value "NO"; otherwise the local test variable *STDM\_horizontal\_data* takes the value "YES".
- 50 Second the *HORIZONTAL\_DELETE\_BY\_RANGE* mode of deletion is investigated.
- If there exists at least one existing STI whose "Critical" field **755** takes the value "YES" and which partially overlaps the range of cells constituted by the concatenation of the two ranges of cells *STDM\_range* and *STDM\_bottom\_range*, or which partially overlaps or is included in the range of cells *STDM\_range*, then the local test variable

*STDM\_horizontal\_range\_critical* takes the value "YES"; otherwise the local test variable *STDM\_horizontal\_range\_critical* takes the value "NO".

- If there exists at least one existing STI whose "Critical" field 755 takes the value "NO" and which partially overlaps the range of cells constituted by the concatenation of the two ranges of cells *STDM\_range* and *STDM\_bottom\_range*, or which partially overlaps or is included in the range of cells *STDM\_range*, then the local test variable *STDM\_horizontal\_range\_other* takes the value "YES"; otherwise the local test variable *STDM\_horizontal\_range\_other* takes the value "NO".

- If all the cells within the range of cells *STDM\_range* are empty (containing none data), then the local test variable *STDM\_horizontal\_range\_data* takes the value "NO"; otherwise the local test variable *STDM\_horizontal\_range\_data* takes the value "YES".

Third the VERTICAL\_DELETE mode of deletion is investigated.

- If there exists at least one existing STI whose "Critical" field 755 takes the value "YES" and which partially overlaps the range of cells made of the entire columns where is located the currently selected range of cells *STDM\_range*, or which is included in the range of cells made of the entire columns where is located the currently selected range of cells *STDM\_range*, then the local test variable *STDM\_vertical\_critical* takes the value "YES"; otherwise the local test variable *STDM\_vertical\_critical* takes the value "NO".

- If there exists at least one existing STI whose "Critical" field 755 takes the value "NO" and which partially overlaps the range of cells made of the entire columns where is located the currently selected range of cells *STDM\_range*, or which is included in the range of cells made of the entire columns where is located the currently selected range of cells *STDM\_range*, then the local test variable *STDM\_vertical\_other* takes the value "YES"; otherwise the local test variable *STDM\_vertical\_other* takes the value "NO".

- If all the cells within the range of cells made of the entire columns where is located the currently selected range of cells *STDM\_range* are empty (containing no data), then the local test variable *STDM\_vertical\_data* takes the value "NO"; otherwise the local test variable *STDM\_vertical\_data* takes the value "YES".

Fourth the VERTICAL\_DELETE\_BY\_RANGE mode of deletion is investigated.

- If there exists at least one existing STI whose "Critical" field 755 takes the value "YES" and which partially overlaps the range of cells constituted by the concatenation of the two ranges of cells *STDM\_range* and *STDM\_right\_range*, or which partially overlaps or is included in the range of cells *STDM\_range*, then the local test variable *STDM\_vertical\_range\_critical* takes the value "YES"; otherwise the local test variable *STDM\_vertical\_range\_critical* takes the value "NO".

- If there exists at least one existing STI whose "Critical" field 755 takes the value "NO" and which partially overlaps the range of cells constituted by the concatenation of the two ranges of cells *STDM\_range* and *STDM\_right\_range*, or which partially overlaps or is included in the range of cells *STDM\_range*, then the local test variable *STDM\_vertical\_range\_other* takes the value "YES"; otherwise the local test variable *STDM\_vertical\_range\_other* takes the value "NO".

- If all the cells within the range of cells *STDM\_range* are empty (containing no data), then the local test variable *STDM\_vertical\_range\_data* takes the value "NO"; otherwise the local test variable *STDM\_vertical\_range\_data* takes the value "YES".

Fifth the CONTENT\_DELETE mode of deletion is investigated.

- If there exists at least one existing STI whose "Critical" field 755 takes the value "YES" and whose intersection with the range of cells *STDM\_range* contains at least one element or meta-element cell specified as "OUT" cell, then the local test variable *STDM\_content\_critical* takes the value "YES"; otherwise the local test variable *STDM\_content\_critical* takes the value "NO".

- If there exists at least one existing STI whose "Critical" field 755 takes the value "NO" and whose intersection with the range of cells *STDM\_range* contains at least one

element or meta-element cell specified as "OUT" cell, then the local test variable *STDM\_content\_other* takes the value "yes"; otherwise the local test variable *STDM\_content\_other* takes the value "no".

- If all the cells within the range of cells *STDM\_range* are empty (containing no data), then the local test variable *STDM\_content\_data* takes the value "no"; otherwise the local test variable *STDM\_content\_data* takes the value "yes".
- At step 1813, a test is performed to check the deletion impact on any existing STI, according to the values assigned during the step 1812 to the local variables
  - *STDM\_horizontal\_critical*,
  - *STDM\_horizontal\_other*,
  - *STDM\_horizontal\_range\_critical*,
  - *STDM\_horizontal\_range\_other*,
  - *STDM\_vertical\_critical*,
  - *STDM\_vertical\_other*,
  - *STDM\_vertical\_range\_critical*,
  - *STDM\_vertical\_range\_other*,
  - *STDM\_content\_critical*,
  - *STDM\_content\_other*.

If none of these local variables takes the value "yes", then control is given to step 1814; otherwise if at least one of these local variables takes the value "yes", then control is given to step 1815.

- At step 1814, the conventional deletion method as used and defined in conventional electronic spreadsheet environments is triggered, and then control is given back to the initial step 1801 for processing any future **STI Deletion Manager** command.

- At step 1815, the ST Delete Manager Dialog Box 1920 is displayed on the display device 106. The label box 1929 is initialized with the reserved value "None". The 15 label boxes 1924 are filled row after row, starting with the top row, from the left to the right, with the values of the following local variables in the following order:

- *STDM\_content\_critical*,
- *STDM\_content\_other*,
- *STDM\_content\_data*,
- *STDM\_horizontal\_critical*,
- *STDM\_horizontal\_other*,
- *STDM\_horizontal\_data*,
- *STDM\_horizontal\_range\_critical*,
- *STDM\_horizontal\_range\_other*,
- *STDM\_horizontal\_range\_data*,
- *STDM\_vertical\_critical*,
- *STDM\_vertical\_other*,
- *STDM\_vertical\_data*,
- *STDM\_vertical\_range\_critical*,
- *STDM\_vertical\_range\_other*,
- *STDM\_vertical\_range\_data*.

Then if the local variable *STDM\_mode* takes the respective value CONTENT\_DELETE, or HORIZONTAL\_DELETE, or HORIZONTAL\_DELETE\_BY\_RANGE, or VERTICAL\_DELETE, or VERTICAL\_DELETE\_BY\_RANGE, then the option button 1930, or 1928, or 1927, or 1926, or 1925 displays alone a black point.

Finally the "Delete" push-button 1923 is disabled as soon as one of the following local variables takes the value "yes":

- *STDM\_content\_critical* (only taken into account if the local variable *STDM\_mode* is equal to CONTENT\_DELETE),
- *STDM\_horizontal\_critical* (only taken into account if the local variable *STDM\_mode* is equal to HORIZONTAL\_DELETE),

- *STDM\_vertical\_critical* (only taken into account if the local variable *STDM\_mode* is equal to *VERTICAL\_DELETE*),
- *STDM\_horizontal\_range\_critical* (only taken into account if the local variable *STDM\_mode* is equal to *HORIZONTAL\_DELETE\_BY\_RANGE*),
- 5 • *STDM\_vertical\_range\_critical* (only taken into account if the local variable *STDM\_mode* is equal to *VERTICAL\_DELETE\_BY\_RANGE*); otherwise the "Delete" push-button 1923 is enabled.
- At step 1816, the method is waiting for any user action on the ST Insert Manager Dialog Box 1920. Such user action is typically resulting from a click with the pointing device 105, but take other similar forms such as, but not limited to a specific combination of key on the keyboard 104, or any other similar means not further specified here.
- 10 • At step 1817, a user action on the ST Insert Manager Dialog Box 1920 is detected. If the user action is a click on the "Delete" push-button 1923, then control is given to step 1819; if the user action is a click on one of the option buttons 1930, or 1928, or 1927, or 1926, or 1925, then control is given to step 1818; if the user action is a click on the "Cancel" push-button 1922, or on the closing-window push-button 1921, then control is given to step 1830.
- 15 • At step 1818, the local variable *STDM\_mode* takes the value *CONTENT\_DELETE*, or *HORIZONTAL\_DELETE*, or *HORIZONTAL\_DELETE\_BY\_RANGE*, or *VERTICAL\_DELETE*, or *VERTICAL\_DELETE\_BY\_RANGE* if the spreadsheet user has respectively clicked with the pointing device 105 on the option button 1930, or 1928, or 1927, or 1926, or 1925. Then control is given to step 1815.
- 20 • At step 1819, the STIT table 750 is visited to remove from it every record 751 corresponding to a STI corrupted by the deletion operation, as identified during the step 1812 for the deletion mode represented by the local variable *STDM\_mode*. Then the STT table 720 is updated to reflect the removal of each STI. For each removed STI, the INSTANCE REFERENCE (IR) field 729c of the "REFERENCED" attribute 729 of the record 721 whose "Name" field 722 is equal to the "S7" field 753 of the record 751 of the STIT table 750 corresponding to the removed STI, is divided by 2 (two). Then control is given to the step 1825.
- 25 • At step 1820, the local variable *STDM\_height* is decremented by 1 (one), as long as its value remains strictly positive. If the decrement has been done, then the currently selected range of cells *STDM\_range* is reduced by removing from the current selection the last row. Then control is given to step 1805.
- 30 • At step 1821, the local variable *STDM\_height* is incremented by 1 (one), as long as its value remains less than the value of the local variable *STDM\_element*. If the increment has been done, then the currently selected range of cells *STDM\_range* is enlarged by adding to the current selection a new row below the last one. Then control is given to step 1805.
- 35 • At step 1822, the local variable *STDM\_critical* is updated in order to swap between the values "YES" and "No". In addition, a check mark is respectively added within or removed from the "Critical" check box 1910 if it was previously absent or present in this same check box 1910. Then the field "Critical" 755 within the record 751 of the STIT table 750, as found at step 1803 is updated with the value of the local variable *STDM\_critical*. Then control is given to step 1805.
- 40 • At step 1823, the local variable *STDM\_mode* takes the value "DELETE\_IN\_FIELDS\_IN\_SELECTED\_RANGE", or "DELETE\_IN\_FIELDS\_IN\_SELECTED\_ROWS", or "DELETE\_SELECTED\_ELEMENTS", or "DELETE\_SELECTED\_INSTANCE", if the spreadsheet user has respectively clicked with the pointing device 105 on the option button 1905, or 1906, or 1912, or 1913. Then control is given to step 1805.
- 45 • At step 1824 a test is performed to check the value of the local variable *STDM\_mode*.
- 50 • If this value is found equal to "DELETE\_IN\_FIELDS\_IN\_SELECTED\_RANGE" then control is given to step 1826;

- if this value is found equal to "DELETE\_IN\_FIELDS\_IN\_SELECTED\_ROWS" then control is given to step 1827;
- if this value is found equal to "DELETE\_SELECTED\_ELEMENTS" then control is given to step 1828;
- 5 • If this value is found equal to "DELETE\_SELECTED\_INSTANCE" then control is given to step 1829.
  
- At step 1825 a test is performed to check the value of the local variable *STDM\_mode*.
  - If this value is found equal to HORIZONTAL\_DELETE then control is given to step 1831;
  - 10 • if this value is found equal to HORIZONTAL\_DELETE\_BY\_RANGE then control is given to step 1833;
  - if this value is found equal to VERTICAL\_DELETE then control is given to step 1832;
  - if this value is found equal to VERTICAL\_DELETE\_BY\_RANGE then control is given to step 1834;
  - If this value is found equal to CONTENT\_DELETE then control is given to step 1837.
- 15 • At step 1826, the "IN" cells belonging to the currently selected range of cells *STDM\_range* are cleared. For this purpose, the "ST" field 753 of the record 751 of the STIT table 750, as identified at step 1803, is visited to get a memory pointer on the STDT table 760 of the ST, which specifies for each meta-element and for each element of the STI what is the associated EP, which in turn indicates which cells are "IN" cells and which cells are "OUT" cells. Then each row of the range of cells *STDM\_range* is selected one after the other, and for each selected row, the corresponding element or MEP is retrieved from the STDT table 760 to determine which cells are "IN" cells. For this purpose, a temporary local variable *STDM\_out\_fields* memorizes the relative positions of all the cells specified as "IN" or "OUT" cells, as an ordered set of IN or OUT values. For instance in an EP made of 5 cells, where only the third and fifth cells are "OUT" cells, this local variable *STDM\_out\_fields* takes the value (IN, IN, OUT, IN, OUT). With the same example, if the selected range of cells was only occupying the second, third and fourth columns of the STI, then the first cell is ignored because although it is an "IN" cell, it falls outside the limits of the range of cells *STDM\_range*, so that only the second and fourth cells are taken into account. Once the "IN" cells belonging to the range of cells *STDM\_range* are determined, these cells are updated by clearing their content.
- 20 • At step 1827, the currently selected range of cells *STDM\_range* is updated in order to align its columns with those occupied by the STI *STDM\_instance\_range*. Then control is given to step 1826.
- 30 • At step 1828, the elements belonging to the rows of the currently selected range of cells *STDM\_range* are removed from the current STI *STDM\_instance\_range*. For this purpose is first selected the range of cells constituted by the same columns as the range of cells *STDM\_instance\_range*, and whose rows are located between the bottom row of the range of cells *STDM\_range* (excluded) and the bottom row of the range of cells *STDM\_instance\_range* (included). Then this selected range of cells is moved upwards, row after row, up to the position where its top row occupies the same row as the top row of the former range of cells *STDM\_range*. For each step of this move, a row within the range of cells *STDM\_range* is removed, so that at the end all the rows of the range of cells *STDM\_range* are removed. Then control is given to step 1836.
- 35 • At step 1829, the range of cells corresponding to the STI *STDM\_instance\_range* becomes a regular ranges of cells and loses its quality of STI. For this purpose, the content of all the cells of this range of cells *STDM\_instance\_range* is cleared, and then this whole range of cells receives the default display attributes defined within the current spreadsheet file. Then control is given to step 1835.
- 40 • At step 1830, the ST Delete Manager Dialog Box 1900 or 1920 is closed so that it disappears from the display device 106. Finally control is given back to the initial step 1801 for processing any future *STI Deletion Manager* command.
- 45 •
- 50 •



- At step 1831, the range of cells *STDM\_range* is selected to become the currently selected range of cells so that *STDM\_height* rows are selected, and then a regular operation of "row deletion" is performed. Then control is given to step 1830.
- 5 ~~At step 1832, the range of cells *STDM\_range* is selected to become the currently~~  
selected range of cells so that *STDM\_width* columns are selected, and then a regular operation of "column deletion" is performed. Then control is given to step 1830.
- At step 1833, the range of cells *STDM\_range* is selected to become the currently selected range of cells so that *STDM\_height* rows are selected, and then a regular operation of "row deletion within selected range" is performed. Then control is given to
- 10 step 1830.
- At step 1834, the range of cells *STDM\_range* is selected to become the currently selected range of cells so that *STDM\_width* columns are selected, and then a regular operation of "column deletion within selected range" is performed. Then control is given to step 1830.
- 15 • At step 1835, the record 751 identified at step 1803 is removed from the STIT table 750. Then the STT table 720 is updated to reflect the removal of this STI. The INSTANCE REFERENCE (IR) field 729c of the "REFERENCED" attribute 729 of the record 721 whose "Name" field 722 is equal to the "ST" field 753 of the record 751 of the STIT table 750 corresponding to the removed STI, is divided by 2 (two), before giving control to the step
- 20 1830.
- At step 1836, the current STI *STDM\_instance\_range* is updated by restoring in all the remaining elements the "OUT" cells to prevent any corruption due to the element deletion. First the STT table 720 is parsed to identify the record 721 whose "Name" field
- 25 722 matches the value of the local variable *ST\_name*. Within this record 721 is retrieved the "Description Ptr" field 724 allowing to locate in memory the STDIT table 760 associated to the ST that the current STI *STDM\_instance\_range* abides by. Then the element pair 762 within this STDIT table 760 is accessed to retrieve the EP, recorded in the local variable *STDM\_profile*. Then the EPT table 710 is parsed to identify a record
- 30 "Description Ptr" field 714 is used to access in memory a description of the EP which indicates which cells are "IN" cells and which cells are "OUT" cells. For this purpose, a temporary local variable *STDM\_out\_fields* memorises the relative positions of all the cells specified as "OUT" cells, as an ordered set of IN or OUT values. For instance with an
- 35 *STDM\_out\_fields* takes the value (IN, IN, OUT, IN, OUT). Then each "OUT" cell of the illustrative range of cells (pointed by the "Description Ptr" field 714 of the record 711 of the EPT table 710 whose "Name" 712 field matches the local variable *STDM\_profile*) is individually copied and pasted onto the cell of the top element of the STI
- 40 *STDM\_instance\_range* which has the same relative column offset within the element (corresponding to a position taking the value "OUT" in the local variable *STDM\_out\_fields*). Then the top element of the STI *STDM\_instance\_range* is selected as the currently selected range of cells. Then each cell within this selection is individually deselected if it corresponds to a position taking the value "IN" in the local variable
- 45 *STDM\_out\_fields*. Within this selection, the leftmost cell is set as the currently selected cell. At this stage, the current selection corresponds to the collection of all the "OUT" cells. Then the current selection is extended to include as many rows as needed below the top element, so that it spreads over all the elements of the STI
- 50 *STDM\_instance\_range*. Then a conventional "copy-down" operation is done to copy the first row onto the below ones, so that all the "OUT" cells of the current STI *STDM\_instance\_range* receive a correct content. Finally the "Element #" field 754 within the record 751 of the STIT table 750, as found at step 1803 is updated with the difference of the local variables *STDM\_element* and *STDM\_height*. Finally control is to step 1830.

- At step 1837, the content of every cell comprised within the currently selected range of cells *STDM\_range* is cleared. Then control is given to step 1830.

#### E8. RSTI Deletion Manager method

5 The method for deleting objects within a RSTI used in the preferred embodiment of the present invention is summarized in flowchart 1840 of FIG 15B. This method can be seen as the processing of the *STI Deletion Manager* command.

- At step 1841, the method is in its default state, waiting for an event to initiate the process.
- 10 • At step 1842, the *RSTI Deletion Manager* command is detected, as a result of a user action. This action can be for instance a specific combination of keys on the keyboard 104, or the click of the pointing device 105 on a specific button, or any other similar means no further specified here.
- At step 1843, some local variables are initialized :
  - 15 • The local variable *csr* ("currently selected range") is a range of cells corresponding to the currently selected range of cells.
  - The local variable *csc* ("currently selected cell") is the individual cell corresponding to the currently selected cell.
  - 20 • The local variable *cRSTITr* ("current RSTIT record") corresponds, if it exists, to the record 2261 of the RSTIT table 2260, the "Address" field 2262 of which belongs to the same sheet as the local variable range of cells *csc*. If the RSTIT table 2260 does not contain any record 2261 with the "Address" field 2262 occupying the same sheet as the local variable range of cells *csc*, then the local variable *cRSTITr* defaults to the value "void".
  - 25 • The local variable *rir* ("recursive instance range") is the range of cells 2001 whose address is given by the "Address" field 2262 of the *cRSTITr* record 2261, if not equal to "void". If the local variable *cRSTITr* takes the value "void", then the local variable *rir* defaults also to the value "void".
  - 30 • The local variable *cRSTIDT* ("current RSTIDT") is the RSTIDT table 2270 pointed by the "RSTIDT Ptr" field 2265 of the *cRSTITr* record 2261, if not void. If the local variable *cRSTITr* takes the value "void", then the local variable *cRSTIDT* defaults also to the value "void".
  - 35 • If the local variable *rir* is not equal to "void", then the local variable *RST\_name* is initialized with the name of the RST abided by the RSTI *rir*. This name is given by the "RST" field 2263 of the *cRSTITr* record 2261 of the RSTIT table 2260 whose "Address" field 2262 belongs to the same sheet as the range of cells *csc*.
  - 40 • The local variable *ir* ("instance range") is a range of cells corresponding, if it exists, to the STI containing the currently selected cell *csc*. If the currently selected cell *csc* does not belong to a STI, then the local variable *ir* takes a default value set to "void". The initialization of this local variable *ir* is determined by comparing the address of the local variable *csc* with the "Address" field 752 of each record 751 of the STIT table 750. For instance, by referring to the FIG 17A, the local variable *ir* takes the value void if the local variable *csc* corresponds to one of the ranges of cells 2024, or 2022, and corresponds to the respective ranges of cells 2034, or 2032 or 2030, or 2031, or 2033, or 2013, if the local variable *csc* corresponds to one of the ranges of cells 2018, or 2019, or 2020, or 2021, or 2023, or 2025.
  - 45 • The local variable *ccirb* ("current cell in recursive body") is a Boolean variable taking the values TRUE or FALSE if the currently selected cell *csc* is respectively located or not within the body part 2003 of the *rir* range of cells 2001. For instance, by referring to the FIG 17A, the local variable *ccirb* takes the value TRUE if the local variable *csc* corresponds to one of the ranges of cells 2018, or 2020, or 2022, or 2023, and the value FALSE if the local variable *csc* corresponds to one of the ranges of cells 2019, or 2021, or 2024, or 2025.
  - 50

- The local variable *cr* ("container row") corresponds, if the local variable *ccirb* is equal to TRUE, to the container row range of cells where the currently selected cell *csc* is located. If the local variable *ccirb* is equal to the value "void", then the local variable *cr* also defaults to the value "void". For instance, by referring to the FIG 17A, the local variable *cr* takes the value void if the local variable *csc* corresponds to one of the ranges of cells 2019, or 2021, or 2024, or 2025 and corresponds to the respective ranges of cells 2008, or 2009, or 2010, or 2010, if the local variable *csc* corresponds to one of the ranges of cells 2023, or 2020, or 2018, or 2022.
- The local variable *csii* ("current selection in instance") is a Boolean variable taking the values TRUE or FALSE if the selected range of cells *csr* is respectively comprised or not within a STI. For instance, by referring to the FIG 17A, the local variable *csii* takes the value TRUE if the local variable *csr* corresponds to one of the ranges of cells 2018, or 2019, or 2020, or 2021, and the value FALSE if the local variable *csr* corresponds to one of the ranges of cells 2022, or 2023, or 2024, or 2025.
- The local variable *ccii* ("current cell in instance") is a Boolean variable taking the values TRUE or FALSE if the currently selected cell *csc* is respectively comprised or not within a STI. For instance, by referring to the FIG 17A, the local variable *ccii* takes the value TRUE if the local variable *csc* corresponds to one of the ranges of cells 2018, or 2019, or 2020, or 2021, or 2023, or 2025, and the value FALSE if the local variable *csc* corresponds to one of the ranges of cells 2022, or 2024.
- The local variable *csib* ("current selection in body") is a Boolean variable taking the values TRUE or FALSE if the selected range of cells *csr* is respectively comprised or not within the body part of a STI. For instance, by referring to the FIG 17A, the local variable *csib* takes the value TRUE if the local variable *csr* corresponds to one of the ranges of cells 2018, or 2019, and the value FALSE if the local variable *csr* corresponds to one of the ranges of cells 2020, or 2021, or 2022, or 2023, or 2024, or 2025.
- The local variable *RSTIDM\_mode* is initialized with the value "del\_rec\_inst".
- At step 1844, a test is performed to determine if the local variable *rir* is void or not. If it is the case, then control is given to step 1845 ; otherwise control is given to step 1846.
- At step 1845, the **STI Deletion Manager** command is invoked (as a sub-routine). When this command completes and returns control to the current process, the control is given to the initial step 1841 for processing any future **RSTI Deletion Manager** command.
- At step 1846, a test is performed to determine if the cell represented by the local variable *csc* is part of the range of cell represented by the local variable *rir*. If it is the case, then control is given to step 1848 ; otherwise control is given to step 1847.
- At step 1847, the conventional deletion method available in existing electronic spreadsheet environments is followed, after having disabled any deletion mode that could pollute the RSTI range *rir*. These polluting deletion modes are identified as follows:
  - If the range of cells *csr* shares some rows with the range of cells *rir*, then the conventional row deletion mode is disabled.
  - If the range of cells *csr* shares some columns with the range of cells *rir*, then the conventional column deletion mode is disabled.
  - If the range of cells *csr* shares some cells with the range of cells *rir*, then the conventional cell content deletion mode is disabled.
- Then control is given to the initial step 1841 for processing any future **RSTI Deletion Manager** command.
- At step 1848, the RSTI Deletion Manager dialog box 1940 is displayed on the display device 106, according to the values of some local variables.
  - The text box 1950 is filled with the value of the local variable *RST\_name*.
  - If the local variable *RSTIDM\_mode* takes the respective values "del\_rec\_inst", or "del\_cont", or "del\_elem", or "del\_inst\_IN", or "del\_elem\_IN", or "del\_select\_IN", then the option button 1944, or 1945, or 1946, or 1947, or 1948, or 1949 is filled with a

black point whereas the other options buttons belonging to the dialog box 1940 are kept void.

- If the local variable *ccirb* is equal to TRUE, then the option button 1945 is enabled, so that any future click on it with the pointing device 105 will be recognized as a valid event. If the local variable *ccirb* is equal to FALSE, then the option button 1945 is disabled, so that any future click on it with the pointing device 105 will not be recognized as a valid event.
  - If the local variable *csib* is equal to TRUE, then the option button 1946 is enabled, so that any future click on it with the pointing device 105 will be recognized as a valid event. If the local variable *csib* is equal to FALSE, then the option button 1946 is disabled, so that any future click on it with the pointing device 105 will not be recognized as a valid event.
  - If the local variable *csii* is equal to TRUE, then the option buttons 1948 and 1949 are enabled, so that any future click on them with the pointing device 105 will be recognized as a valid event. If the local variable *csii* is equal to FALSE, then the option buttons 1948 and 1949 are disabled, so that any future click on them with the pointing device 105 will not be recognized as a valid event.
  - If the local variable *ccii* is equal to TRUE, then the option button 1947 is enabled, so that any future click on it with the pointing device 105 will be recognized as a valid event. If the local variable *ccii* is equal to FALSE, then the option button 1947 is disabled, so that any future click on it with the pointing device 105 will not be recognized as a valid event.
  - At step 1849, the method is waiting for any user action on the RSTI Deletion Manager dialog box 1940. Such user action is typically resulting from a click with the pointing device 105, but take other similar forms such as, but not limited to a specific combination of keys on the keyboard 104, or any other similar means not further specified here.
  - At step 1850, a user action on the RSTI Deletion Manager dialog box 1940 is detected.
    - If the user action is a click with the pointing device 105 on one of the enabled option buttons 1944, or 1945, or 1946, or 1947, or 1948, or 1949, then control is given to step 1851.
    - If the user action is a click with the pointing device 105 on the "Delete" push-button 1942, then control is given to step 1853.
    - If the user action is a click with the pointing device 105 on the "Cancel" push button 1943, or on the closing-window push-button 1941, then control is given to step 1852.
  - At step 1851, the local variable *RSTIDM\_mode* is updated, according to the enabled option button clicked on by the user at step 1850 :
    - If the user has clicked on the option button 1944, then the local variable *RSTIDM\_mode* takes the value "del\_rec\_inst".
    - If the user has clicked on the option button 1945, then the local variable *RSTIDM\_mode* takes the value "del\_cont".
    - If the user has clicked on the option button 1946, then the local variable *RSTIDM\_mode* takes the value "del\_elem".
    - If the user has clicked on the option button 1947, then the local variable *RSTIDM\_mode* takes the value "del\_inst\_IN".
    - If the user has clicked on the option button 1948, then the local variable *RSTIDM\_mode* takes the value "del\_elem\_IN".
    - If the user has clicked on the option button 1949, then the local variable *RSTIDM\_mode* takes the value "del\_select\_IN".
- Then control is given to step 1848.
- At step 1852, the RSTI Deletion Manager dialog box 1940 is closed on the display device 106, and then control is given to the initial step 1841 for processing any future *RSTI Deletion Manager* command.

- At step 1853, a test is performed to check if the local variable *RSTIDM\_mode* takes the value "del\_rec\_inst". If it is the case, then control is given to step 1854; otherwise control is given to step 1855.
- 5 • At step 1854, the current record *cRSTITr* 2261 of the RSTI Table RSTIT 2260 is removed from this table RSTIT 2260, and the associated RSTI Descriptor Table RSTIDT 2270 pointed-by-the-"*RSTIDT Ptr*" field 2265 of the record *cRSTITr* 2261 is deleted. Then the RSTT table 2220 is scanned to identify the record 2221 whose "*Name*" field 2222 is found equal to the local variable *RST\_name*. Once found, the "REFERENCED" attribute 2229 within the "*Type*" field 2227 of this record 2221 is updated by dividing the  
10 "INSTANCE REFERENCE" subfield 2229c by 2 (two). Then control is given to step 1852.
- At step 1855, a test is performed to check if the local variable *RSTIDM\_mode* takes the value "del\_cont". If it is the case, then control is given to step 1856 ; otherwise control is given to step 1858.
- 15 • At step 1856, the container row *cr* is deleted from the current sheet by removing the rows it occupies.
- At step 1857, the STIT table 750 is updated by removing all the records 751 with an "*Address*" field 752 which were pointing within the container row *cr*. The RSTIDT table *cRSTIDT* 2270 is then updated by removing the record 2271 corresponding to the deleted container row *cr*. Then control is given to step 1852.
- 20 • At step 1858, a test is performed to check if the local variable *RSTIDM\_mode* takes the value "del\_elem". If it is the case, then control is given to step 1859 ; otherwise control is given to step 1861.
- At step 1859, the elements belonging to the rows of the currently selected range of cells *csr* are removed from the STI *ir*. For this purpose is first selected the range of cells  
25 constituted by the same columns as the range of cells *ir*, and whose rows are located between the bottom row of the range of cells *csr* (excluded) and the bottom row of the range of cells *ir* (included). Then this selected range of cells is moved upwards, row after row, up to the position where its top row occupies the same row as the top row of the former range of cells *csr*. For each step of this move, a row within the range of cells *csr*  
30 *ir* removed, so that at the end all the rows of the range of cells *csr* are removed. If the result of this element removal is to leave one empty row or a plurality of empty rows at the bottom of the container row range of cells *cr*, then this empty row or this plurality of empty rows is removed.
- At step 1860, the STI *ir* is updated by restoring in all the remaining elements the "OUT" cells to prevent any corruption due to the element deletion. The followed method is the  
35 same as the one described at step 1836 of the **STI Deletion Manager** command, and is not repeated here. Then the STIT table 750 is changed by updating the record 751 corresponding to the STI *ir*: the "*Address*" field 752 is updated to reflect the new range address of *ir*, and the "*Element #*" field 754 is updated to reflect the new number of  
40 elements within the STI *ir*. Then the RSTIDT table *cRSTIDT* 2270 is updated by modifying in the record 2271 the attributes corresponding to the modified STI *ir* and (potentially) modified container row *cr*. Within the cell 2280 associated with the STI *ir*, the attribute "*STI\_row*" 2279 is updated to reflect the new number of rows within the STI *ir*, the attribute "*Container\_row*" 2281 is updated to reflect the new number of container  
45 rows, and the "*Container\_range*" attribute 2276 is updated to reflect the new address of the container comprising the STI *ir*. If one row or a plurality of rows were removed at the end of the step 1859, then the other cells 2280 of the same record 2271 are also updated by modifying similarly the attributes "*Container\_row*" 2281 and "*Container\_range*" 2276. Then control is given to step 1852.
- 50 • At step 1861, a test is performed to check if the local variable *RSTIDM\_mode* takes the value "del\_elem\_IN". If it is the case, then control is given to step 1862 ; otherwise control is given to step 1863.

- At step 1862, the currently selected range of cells *csr* is updated in order to align its columns with those occupied by the *STI ir*. Then control is given to step 1865.
- At step 1863, a test is performed to check if the local variable *RSTIDM\_mode* takes the value "del\_inst\_IN". If it is the case, then control is given to step 1864 ; otherwise control is given to step 1865.
- At step 1864, the currently selected range of cells *csr* is set equal to the local variable range of cells *ir*, so that it becomes the new currently selected range of cells.
- At step 1865, the "IN" cells belonging to the currently selected range of cells *csr* are cleared. The followed method is the same as the one described at step 1826 of the *STI Deletion Manager* command, and is not repeated here. Then control is given to step 1852.

#### E9. RST Instanciator method

The method for instanciating a RST used in the preferred embodiment of the present invention is summarized in flowchart 2100 of FIG 18A and 18B. This method can be seen as the processing of the *ST Instanciator* command.

- At step 2101, the method is in its default state, waiting for an event to initiate the process.
- At step 2102, the *RST Instanciator* command is detected, as a result of a user action. This action can be for instance a specific combination of keys on the keyboard 104, or the click of the pointing device 105 on a specific button, or any other similar means no further specified here.
- At step 2103, the command parameter is retrieved and some local variables are initialized:
  - The command parameter is recorded in the *RST\_Name* variable.
  - The local variable *Element#* is initialized with the value 0 (zero).
  - The local variable *too\_wide* is initialized with the default value FALSE.
  - The local variable *too\_high* is initialized with the default value FALSE.
  - The local variable *Max\_col* is initialized with the maximum number of available columns on a sheet.
  - If the local variable *Max\_row* is initialized with the maximum number of available rows on a sheet.
  - The local variable *STI\_present* is initialized with the default value FALSE.
  - The local variable *RSTI\_busy* is initialized with the default value FALSE.
  - The local variable *RSTI\_top\_left\_cell* is initialized as being the currently selected cell.
- At step 2104, the RSTT table 2220 is parsed to identify the record 2221 (identified by the local variable *Curr\_RSTT\_rec*) whose "Name" field 2222 is equal to the command parameter *RST\_Name*. Then the local variable *RSTI\_E#* is set equal to the value of the "Min Element#" field 2225 of this record *Curr\_RSTT\_rec* 2221.
- At step 2105, the local variable *Curr\_RSTDT* is set equal to the RSTDT table 2250 pointed by the "Description Ptr" field 2224 of the record *Curr\_RSTT\_rec* 2221. Then the local variable *Curr\_RSTDT\_rec* is set equal to the first single-cell record 2251 of the *Curr\_RSTDT* table 2250. Then the local variable *Curr\_RET\_rec* is set equal to the record 2211 of the RET table 2210, with a "Name" field 2212 equal to the local variable *Curr\_RSTDT\_rec*. Then the local variable *Curr\_RED\_RoC* is set equal to the range of cells pointed by the "Description Ptr" field 2214 of the record *Curr\_RET\_rec* 2211.
- At step 2106, a RSTIDT table 2270 is loaded in memory and named through the local variable *Curr\_RSTIDT*. This table has a number of rows equal to the numbers of rows of the *Curr\_RSTDT* table 2250, incremented by the value of the local variable *RSTI\_E#* and decremented by 1 (one). This table has a number of columns equal to the number of columns of the *Curr\_RED\_RoC* range of cells. Then the local variable *Curr\_RSTIDT\_rec* is initialized as the first record 2271 of the *Curr\_RSTIDT* table 2270.



- At step 2107, the local variable *Curr\_RSTIDT\_cell* is initialized as the first cell 2280 of the *Curr\_RSTIDT\_rec* 2271. Then the local variable *Curr\_REC\_RoC\_cell* is initialized as the first cell of the *Curr\_REC\_RoC* range of cells.
- At step 2108, the "STI\_col" field 2278 of the *Curr\_RSTIDT\_cell* 2280 is set equal to the value returned by the function STI\_col when called with the unique parameter equal to the value of the local variable *Curr\_RET\_RoC\_cell*. Then the "STI\_row" field 2279 of the *Curr\_RSTIDT\_cell* 2280 is set equal to the value returned by the function STI\_row when called with the two parameters respectively equal to the value of the local variable *Curr\_RET\_RoC\_cell* and to 0 (zero). Then the "ST\_name" field 2280 of the *Curr\_RSTIDT\_cell* 2280 is set equal to the value of the local variable *Curr\_RET\_RoC\_cell*.
- At step 2109, a test is performed to check if the cell represented by the local variable *Curr\_RSTIDT\_cell* 2280 is the last cell of the record represented by the local variable *Curr\_RSTIDT\_rec* 2271. If it is the case, then control is given to step 2111; otherwise control is given to step 2110.
- At step 2110, the cell located on the right of the cell represented by the local variable *Curr\_RSTIDT\_cell* 2280 becomes the new *Curr\_RSTIDT\_cell* 2280. Then the cell located on the right of the cell represented by the local variable *Curr\_RET\_RoC\_cell* becomes the new *Curr\_RET\_RoC\_cell*. Then control is given to step 2108.
- At step 2111, a test is performed to check if the record represented by the local variable *Curr\_RET\_rec* 2211 describes a RE. This can be determined if the "META" attribute 2218 of the "Type" field 2217 of the *Curr\_RET\_rec* record 2211 is equal to the value "NO". If it is the case, then control is given to step 2112; otherwise control is given to step 2114.
- At step 2112, the local variable *Element#* is incremented by 1 (one).
- At step 2113, a test is performed to determine if the local variable *Element#* is equal to the local variable *RSTI\_E#*. If it is the case, then control is given to step 2114; otherwise control is given to step 2115.
- At step 2114, a test is performed to check if the cell represented by the local variable *Curr\_RSTIDT\_cell* 2280 is the last cell of the record represented by the local variable *Curr\_RSTIDT\_rec* 2271. If it is the case, then control is given to step 2116; otherwise control is given to step 2117.
- At step 2115, the record following the *Curr\_RSTIDT\_rec* record 2271 in the *Curr\_RSTIDT* table 2270 becomes the new *Curr\_RSTIDT\_rec* record 2271. Then control is given to step 2107.
- At step 2116, the record following the *Curr\_RSTDT\_rec* record in the *Curr\_RSTDT* table 2250 becomes the new *Curr\_RSTDT\_rec*. Then control is given to step 2115.
- At step 2117, for each cell *Curr\_RSTIDT\_cell* 2280 belonging to the *Curr\_RSTIDT* table 2270, the "container\_row" attribute 2281 is set equal to the maximum value of the "STI\_row" attribute 2279 of the cells *Same\_row\_cell* located within the *Curr\_RSTIDT* table 2270 on the same row as *Curr\_RSTIDT\_cell*. Then for each cell *Curr\_RSTIDT\_cell* 2280 belonging to the *Curr\_RSTIDT* table 2270, the "container\_col" attribute 2277 is set equal to the maximum value of the "STI\_col" attribute 2278 of the cells *Same\_col\_cell* located within the *Curr\_RSTIDT* table 2270 on the same column as *Curr\_RSTIDT\_cell*.
- At step 2118, the local variable *RSTI\_col* is set equal to the sum of the "container\_col" attributes 2277 of the cells belonging to the first row of the *Curr\_RSTIDT* table 2270. Then the local variable *RSTI\_row* is set equal to the sum of the "container\_row" attributes 2281 of the cells belonging to the first column of the *Curr\_RSTIDT* table 2270.
- At step 2119, a test is performed to determine if the sum of the local variable *RSTI\_col* and of the column index of the individual cell *RSTI\_top\_left\_cell* decremented by 1 (one) is strictly greater than the local variable *Max\_col*. If it is the case, then control is given to step 2120; otherwise control is given to step 2121.
- At step 2120, the local variable *too\_wide* is set equal to the value TRUE.

- At step 2121, a test is performed to determine if the sum of the local variable *RSTI\_row* and of the row index of the individual cell *RSTI\_top\_left\_cell* decremented by 1 (one) is strictly greater than the local variable *Max\_row*. If it is the case, then control is given to step 2122; otherwise control is given to step 2123.
- 5 • At step 2122, the local variable *too\_high* is set equal to the value TRUE.
- At step 2123, a test is performed to determine if there is any existing STI present on the same sheet as the individual cell *RSTI\_top\_left\_cell*. This test can simply be done by parsing the STIT table 750 for identifying any record 751 with an "Address" field 752 pointing to the same sheet as the individual cell *RSTI\_top\_left\_cell*. If it is the case, then control is given to step 2124; otherwise control is given to step 2125.
- 10 • At step 2124, the local variable *STI\_present* is set equal to the value TRUE.
- At step 2125, the local variable *RSTI\_range* is initialized as being the range of cells with *RSTI\_top\_left\_cell* as the top left cell, with a number of rows equal to the value of the local variable *RSTI\_row*, and with a number of columns equal to the value of the local variable *RSTI\_col*.
- 15 • At step 2126, a test is performed to check if there is any data present within the range of cells *RSTI\_range*. If it is the case, then control is given to step 2127; otherwise control is given to step 2128.
- At step 2127, the local variable *RSTI\_busy* is set equal to the value TRUE.
- 20 • At step 2128, the RST Instanciator dialog box 2300 is displayed on the display device 106. Within this dialog box 2300, the text field 2302 is filled with the value of the local variable *RST\_name*, the text field 2311 is filled with the value of the local variable *RSTI\_E#*, the text field 2304 is filled with the value of the local variable *too\_wide*, the text field 2305 is filled with the value of the local variable *too\_high*, the text field 2306 is filled with the value of the local variable *STI\_present*, the text field 2307 is filled with the value of the local variable *RSTI\_busy*. The "Create Instance" push-button 2310 is enabled if and only if the three local variables *too\_wide*, *too\_high* and *STI\_present* take the same value FALSE. The "Create instance in a new sheet" push-button 2309 is enabled if and only if the two local variables *too\_wide* and *too\_high* take the same value FALSE.
- 25 • At step 2129, the method is waiting for any user action on the RST Instanciator dialog box 2300. Such user action is typically resulting from a click with the pointing device 105, but take other similar forms such as, but not limited to a specific combination of keys on the keyboard 104, or any other similar means not further specified here.
- 30 • At step 2130, a user action on the RST Instanciator dialog box 2300 is detected.
  - 35 • If the user action is a click with the pointing device 105 on one "Up" arrow of the spin-button 2303, then control is given to step 2133.
  - If the user action is a click with the pointing device 105 on one "Down" arrow of the spin-button 2303, then control is given to step 2134.
  - 40 • If the user action is a click with the pointing device 105 on the "Create instance" push-button 2310, then control is given to step 2138.
  - If the user action is a click with the pointing device 105 on the "Create instance in a new sheet" push-button 2309, then control is given to step 2136.
  - If the user action is a click with the pointing device 105 on the "Cancel" push button 2308, or on the closing-window push-button 2301, then control is given to step 2131.
- 45 • At step 2131, the range of cells *Curr\_RSTIDT* is released from memory.
- At step 2132, the RST Instanciator dialog box 2300 is closed on the display device 106 and then control is given back to the initial step 2101 for processing any future *RST Instanciator* command.
- At step 2133, the local variable *RSTI\_E#* is incremented by 1 (one).
- 50 • At step 2134, the local variable *RSTI\_E#* is decremented by 1 (one).
- At step 2135, the range of cells *Curr\_RSTIDT* is released from memory, and then control is given to the step 2105.
- At step 2136, a new sheet is created and named *curr\_sheet*.

- At step 2137, the top left cell of the sheet *curr\_sheet* becomes the new individual cell *RSTI\_top\_left\_cell*.
- At step 2138, the local variable *STI\_mode* is initialized with the value *OVERLAY*. Then the local variable *STI\_critical* is initialized with the value *YES*. Then the local variable *Curr\_RSTIDT\_rec* is initialized as being the first record 2271 of the *Curr\_RSTIDT* table 2270. Then the local variable *Curr\_RSTIDT\_cell* is initialized as being the first cell 2280 of the record *Curr\_RSTIDT\_rec* 2271. Then the local variable *Curr\_cell* is initialized as being equal to *RSTI\_top\_left\_cell*.
- At step 2139, the "container\_range" attribute 2276 of the *Curr\_RSTIDT\_cell* 2280 is initialized as the range of cell having as the top left cell the individual cell *Curr\_cell*, having a number of rows equal to the value of the "container\_row" attribute 2281, and having a number of columns equal to the value of the "container\_col" attribute 2277.
- At step 2140, the local variable *STI\_range* is set equal to the "container\_range" attribute 2276 of the *Curr\_RSTIDT\_cell* 2280. Then the local variable *ST\_name* is set equal to the "ST\_name" attribute 2280 of the *Curr\_RSTIDT\_cell* 2280. Then the local variable *STI\_element* is set equal to the "Min Element#" field 2225 of the record 721 of the STT table 720 with a "Name" field 722 equal to *ST\_Name*.
- At step 2141, the *CreateSTI* command is invoked (as a sub-routine). When this command completes and returns control to the current process, the control is given to the next step 2142.
- At step 2142, the "STIT\_rec\_ptr" attribute 2282 of the *Curr\_RSTIDT\_cell* 2280 is set as pointing to the STIT record 751 that has just been created during the previous step 2141.
- At step 2143, a test is performed to check if the cell represented by the local variable *Curr\_RSTIDT\_cell* 2280 is the last cell of the record represented by the local variable *Curr\_RSTIDT\_rec* 2271. If it is the case, then control is given to step 2143; otherwise control is given to step 2144.
- At step 2144, the individual cell *curr\_cell* is moved to the right by a number of columns equal to the value of the "container\_col" attribute 2277 of *Curr\_RSTIDT\_cell* 2280. Then the cell located on the right of the individual cell *Curr\_RSTIDT\_cell* 2280 becomes the new *Curr\_RSTIDT\_cell* 2280.
- At step 2145, a test is performed to check if the record represented by the local variable *Curr\_RSTIDT\_rec* 2271 is the last record of the RSTIDT table represented by the local variable *Curr\_RSTIDT* 2270. If it is the case, then control is given to step 2147; otherwise control is given to step 2146.
- At step 2146, the individual cell *RSTI\_top\_left\_cell* is moved down by a number of rows equal to the value of the "container\_row" attribute 2281 of the *Curr\_RSTIDT\_cell* 2280. Then the individual cell *curr\_cell* is set equal to the individual cell *RSTI\_top\_left\_cell*. Then the record 2271 following *Curr\_RSTIDT\_rec* in *Curr\_RSTIDT* 2270 becomes the new record *Curr\_RSTIDT\_rec* 2271. Then the first cell of *Curr\_RSTIDT\_rec* 2271 becomes the new individual cell *Curr\_RSTIDT\_cell* 2280.
- At step 2147, a new record 2261 is created in the RSTIT table 2260 for describing the RSTI that has just been created. The "Address" field 2262 is filled with the address of the *rir* range of cell 2001. The "RST" field 2263 is filled with the local variable *RST\_Name*. The "Element #" field 2264 is filled with the local variable *Element#*. The "RSTIDT Pt" field 2265 is filled with the local variable *Curr\_RSTIDT*. The "Header Size" field 2266 is filled with the number of rows of the container rows constituting the RSTI header 2002. The "Footer Size" field 2267 is filled with the number of rows of the container rows constituting the RSTI footer 2004. Then the RSTT table 2220 is scanned to identify the record 2221 whose "Name" field 2222 is found equal to the local variable *RST\_name*. Once found, the "REFERENCED" attribute 2229 within the "Type" field 2227 of this record 2221 is updated by multiplying the "INSTANCE REFERENCE" subfield 2229c by 2 (two). Then control is given to step 2132.

**E10. RE Editor method**

The method for creating or updating RE's or meta-elements used in the preferred embodiment of the present invention is summarized in flowchart 2340 of FIG 20C. This method can be seen as the processing of the *RE Editor* command.

- 5 • At step 2341, the method is in its default state, waiting for an event to initiate the process.
- At step 2342, the *RE Editor* command is detected, as a result of an user action. This action can be for instance:
  - 10 • a specific combination of key on the keyboard 104, or
  - the click of the pointing device 105 on a specific button, or
  - any other similar means not further specified here.
- At step 2343, the parameter of the command is retrieved. It corresponds to a mandatory parameter *RE\_name* which can either take a reserved value "NEW" or another value corresponding to a character string name, as found in the "Name" field 2232 of a record 2231 within the RSTMT table 2230. This parameter is recorded as a local variable.
- 15 • At step 2344, some local variables are initialized: the local variable *RE\_meta* is set to the value "no", the local variable *RE\_size* is set to the value 3 (three), and the local variable *RE\_rank* is set to the value 1 (one).
- At step 2345, a test is performed to determine the value taken by the local variable *RE\_name*. If found equal to "NEW", then control is given to step 2349; otherwise control is given to step 2346.
- 20 • At step 2346, the RET table 2210 is looked up to locate a record 2211 whose "Name" field 2212 is found equal to the value taken by the local variable *RE\_name*. If such a record is found, then control is given to step 2348; otherwise control is given to step 2347.
- 25 • At step 2347, an exception handler is invoked to treat this "should not occur" condition. Such operation is implementation dependent and can take different forms such as the display on the display device 106 of an error message pop-up window. Then control is given to step 2341.
- 30 • At step 2348,
  - the local variable *RE\_meta* is set to the value "YES" or "NO" according to the value of the "META" attribute 2218 within the "Type" field 2217 of the record 2211 found at step 2346,
  - the local variable *RE\_size* is set to the value found in the "Column #" field 2216 of the record 2211 found at step 2346, and
  - 35 • the memory location pointed by the "Description Ptr" field 2214 of the record 2211 found at step 2346 is copied onto a temporary buffer recorded as the local variable *RE\_buffer*.
- Then control is given to step 2350.
- 40 • At step 2349, a new name for the newly created RE is determined, according to a name string taking in a preferred embodiment of the present invention the form "New XX" where XX corresponds to a counter value ensuring the name uniqueness with respect to all the names previously defined and recorded in the "Name" fields 702, 712, 722, 2212 and 2222 found in the respective records 701, 711, 721, 2211 and 2221 of the respective tables EFT 700, EPT 710, STT 720, RET 2210 and RSST 2220. Any other similar conventional means could be used instead without departing from the spirit of the invention, as long as the uniqueness of the newly created name is ensured.
- 45 Then the new name is recorded in the local variable *RE\_name*. Then memory space is allocated within the main memory 102 to later record the illustrative range of cells for the RE or RME. This allocated memory, recorded as the local variable *RE\_buffer* is part of the memory space corresponding to the currently opened electronic spreadsheet file.
- 50 Then a new record 2211 is created in the RET table 2210, and this new record 2211 is initialized as follows:

- the "Name" field **2212** is set to the value of the local variable *RE\_name* ;
- the "Last Change Date" field **2213** is set to the system time reference, as known by the central processor **101** ;
- the "Description Ptr" field **2214** is set to the memory location *RE\_buffer* which has just been allocated ;

- the "Row-#" field **2215** is set to the value 1 (as-in-the-preferred embodiment of the present invention the RST's are managed in a 2D environment; this field would carry the number of defined rows for the created RE in a 3D environment) ;

- the "Column #" field **2216** is set to the value of the local variable *RE\_size* ;
- the "Type" field **2217** is set as follows: the attribute "META" **2218** is set equal to the value of the local variable *RE\_meta*, and the attribute "REFERENCED" **2219** is initialized as follows:

- The "OWN REFERENCE" (OR) subfield **2219a** is initialized with a prime number not yet assigned to any other OR subfield **709a**, or **719a**, or **729a**, or **780a**, or **2219a**, or **2229a**, or **2240a**. Various conventional techniques can be used for identifying a prime number, and are not further detailed here.

- The "FILIALION REFERENCE" (FR) subfield **2219b** is initialized according to the following formula, where the F set corresponds to the set of ST's constituting the new RE or meta-element, according to the structure recorded in the "Description Ptr" field **2214**:

$$FR = \prod_{i \in F} OR_i \times LCM(\{FR_i\}_{i \in F})$$

- The "INSTANCE REFERENCE" (IR) subfield **2219c** is initialized with the value 1 (one).
- The "REFERENCED OBJECT" (RO) subfield **2219d** is initialized with the following formula, where the P set corresponds to the set of RST's:

$$RO = \text{"YES"} \text{ if } LCM(\{FR_i\}_{i \in P}) \bmod OR = 0;$$

$$RO = \text{"NO"} \text{ otherwise.}$$

- The "SELECTED CHILDREN" (SC) subfield **2219e** is initialized with the following formula, where the S set corresponds to the set of selected objects (having the "SELECTED" attribute **2242** equal to the value "YES" in the RSTMT table **2230**):

$$SC = \text{"YES"} \text{ if } LCM(\{FR_i\}_{i \in S}) \bmod OR = 0 \text{ \#OR\# } RSTE\_name \in S;$$

$$SC = \text{"NO"} \text{ otherwise.}$$

Then control is given to step **2350**.

- At step **2350**, the RE Editor Dialog Box **2321** is displayed on the display device **106**.
  - The label box **2324** is initialized with the value of the local variable *RE\_name*.
  - The top option button **2331** (respectively bottom option button **2330**) is filled with a black point if the local variable *RE\_meta* is found equal to "no" (respectively "yes").
  - The text box **2326** is filled with the value of the local variable *RE\_size*.
  - The push-button "Save" **2333** is enabled if the local variable *RE\_size* is found equal to the "Column #" field **2216** of the current record **2211**, or if the attribute "REFERENCED" **2219** within the "Type" field **2217** of this same record **2211** is found with the subfield "REFERENCED OBJECT" **2219d** (RO) equal to "no", so that any future click with the pointing device **105** on this push-button "Save" **2333** will be recognized as a valid event.
  - The push-button "Save" **2333** is disabled otherwise (local variable *RE\_size* is not found equal to the "Column #" field **2216** of the current record **2211**, and the attribute "REFERENCED" **2219** within the "Type" field **2217** of this same record **2211** is found with the subfield "REFERENCED OBJECT" **2219d** (RO) equal to "yes"), so that any future click with the pointing device **105** on this push-button "Save" **2333** will not be recognized as an event.
  - The text box **2335** is initialized with the value of the local variable *RE\_rank*.
  - The list box **2334** is initialized with the content of the cell belonging to *RE\_buffer* and whose offset is equal to *RE\_rank*. The list of names available within this list box **2334**

(by clicking on the spin button 2328) is constituted by the names of the ST's recorded in the STT table 720.

- At step 2351, the method is waiting for any user action on the RE Editor Dialog Box 2321. Such user action is typically resulting from a click with the pointing device 105, but take other similar forms such as, but not limited to a specific combination of key on the keyboard 104, or any other similar means not further specified here.
- At step 2352, a user action on the RE Editor Dialog Box 2321 is detected.
  - If the user action is a click on the spin button 2328, to select a ST name, then control is given to step 2353;
  - if the user action is a click on the push-button "Save" 2333, then control is given to step 2354;
  - if the user action is a click on the push-button "Save As" 2332, then control is given to step 2355;
  - if the user action is a click on the spin button 2329, then control is given to step 2358;
  - if the user action is a click on the spin button 2327, then control is given to step 2359;
  - if the user action is a click on one of the two option buttons 2330 or 2331, then control is given to step 2360;
  - if the user action is a click on the push-button "Done" 2323, or on the closing-window push-button 2322, then control is given to step 2361.
- At step 2353, the local variable *RE\_buffer* is updated by setting equal to the content of the list box 2334 the content of the cell with offset equal to the value of the local variable *RE\_rank*. Then control is given to step 2350.
- At step 2354, the RET table 2210 is updated and saved as part of the electronic spreadsheet file by refreshing the record 2211 whose "Name" field 2212 is equal to the local variable *RE\_name*. For this purpose,
  - the "Last Change Date" field 2213 is set to the system time reference, as known by the central processor 101 ;
  - the "Column #" field 2216 is set to the value of the local variable *RE\_size* ; and
  - the "Type" field 2217 is set as follows: the attribute "META" 2218 is set equal to the value of the local variable *RE\_meta*.

In addition the range of cells *RE\_buffer* illustrating the current definition of the RE or meta-element is copied onto the memory location pointed by the "Description Ptr" field 2214. Then control is given to step 2350.
- At step 2355, a test is performed on the value found in the text box 2325 to determine if it corresponds to a valid new name. The corresponding criteria are implementation dependent and may take different forms without departing from the spirit of the invention, as long as the new proposed name is a unique character string against all the already defined names recorded in the "Name" fields 702, 712, 722, 2212 and 2222. If validity and uniqueness are proven, then control is given to step 2356; otherwise control is given to step 2357.
- At step 2356, memory space is allocated within the main memory 102 to later record the illustrative range of cells for the EF or MEF. This allocated memory is part of the memory space corresponding to the currently opened electronic spreadsheet file. Then a new record 2211 is created in the RET table 2210 which is saved as part of the electronic spreadsheet file, and this new record 2211 is initialized as follows:
  - the "Name" field 2212 is set to the value found in the text box 2325 and validated at step 2355;
  - the "Last Change Date" field 2213 is set to the system time reference, as known by the central processor 101 ;
  - the "Description Ptr" field 2214 is set to the memory location *RE\_buffer* which has just been allocated ;



- the "Row #" field **2215** is set to the value 1 (as in the preferred embodiment of the present invention the RST's are managed in a 2D environment; this field would carry the number of defined rows for the created RE in a 3D environment) ;
- the "Column #" field **2216** is set to the value of the local variable *RE\_size*;
- the "Type" field **2217** is set as follows: the attribute "META" **2218** is set equal to the value of the local variable *RE\_meta*, and the attribute "REFERENCED" **2219** is initialized as follows:

- The "OWN REFERENCE" (OR) subfield **2219a** is initialized with a prime number not yet assigned to any other subfield **709a**, or **719a**, or **729a**, or **780a**, or **2219a**, or **2229a**, or **2240a**. Various conventional techniques can be used for identifying a prime number, and are not further detailed here.
- The "FILIAION REFERENCE" (FR) subfield **2219b** is initialized according to the following formula, where the F set corresponds to the set of ST's constituting the new RE or meta-element, according to the structure recorded in the "Description Ptr" field **2214**:

$$FR = \prod_{i \in F} OR_i \times LCM(\{FR_i\}_{i \in F})$$

- The "INSTANCE REFERENCE" (IR) subfield **2219c** is initialized with the value 1 (one).
- The "REFERENCED OBJECT" (RO) subfield **2219d** is initialized with the following formula, where the P set corresponds to the set of RST's:

$$RO = \text{"YES"} \text{ if } LCM(\{FR_i\}_{i \in P}) \bmod OR = 0;$$

$$RO = \text{"NO"} \text{ otherwise.}$$

- The "SELECTED CHILDREN" (SC) subfield **2219e** is initialized with the following formula, where the S set corresponds to the set of selected objects (having the "SELECTED" attribute **2242** equal to the value "YES" in the RSTMT table **2230**):

$$SC = \text{"YES"} \text{ if } LCM(\{FR_i\}_{i \in S}) \bmod OR = 0 \text{ or } \# RSTE\_name \in S;$$

$$SC = \text{"NO"} \text{ otherwise.}$$

Then control is given to step **2350**.

- At step **2357**, a warning message notification is issued for informing the user that a valid and unique name must be specified in the text box **2325** prior to clicking on the "Save As" push-button **2332**. This can typically be done by displaying on the display device **106** a warning message in a pop-up window, or in a status bar area, but any other similar means could be used instead, without departing from the spirit of the invention. Once the user has acknowledged this notification message through conventional means such as clicking with the pointing device **105** on an "OK" push-button present within a warning message pop-up window, or any other similar means without departing from the spirit of the invention, control is given to step **2350**.
- At step **2358**, the local variable *RE\_rank* is decremented by 1 (one) as long as it remains strictly positive if the user has clicked with the pointing device **106** on the down side of the spin button **2329**, and the local variable *RE\_rank* is incremented by 1 (one) as long as it remains lower than or equal to the value of the local variable *RE\_size*, if the user has clicked with the pointing device **106** on the up side of the spin button **2329**. Then control is given to step **2350**.
- At step **2359**, the local variable *RE\_size* is either incremented or decremented by 1 (one) according to the direction (up or down) specified by the pointing device **105** on the spin button **2327**, and as long as its value remains positive and less than or equal to an upper limit set equal to 254 in a preferred embodiment of the present invention. Then control is given to step **2350**.
- At step **2360**, the local variable *RE\_meta* is updated, so that its value becomes "YES" (respectively "NO") if the bottom option button **2330** (respectively the top option button **2331**) has been clicked on. Then control is given to step **2350**.
- At step **2361**, the RE Editor Dialog Box **2321** is closed so that it disappears from the display device **106**. Finally control is given back to the initial step **2341** for processing any future *RE Editor* command.

**E11. STI Column/Row counter method**

The method for counting the number of columns or rows within a STI used in the preferred embodiment of the present invention is summarized in flowcharts 2400 and 2420 of FIG 21A and 21B. These methods can be seen as the processing of the *STI\_Row* and *STI\_col* functions.

- At step 2401, the first method is in its default state, waiting for a call to the *STI\_Row* function.
- At step 2402, the *STI\_Row* function call is detected, as a result of a user action. The function is called with two parameters named *ST\_Name* and *STI\_Element*.
- 10 • At step 2403, the first record 721 of the STT table 720 is set as *Curr\_Record*.
- At step 2404, the fields Name 722, Min Element# 725, and Max Element# 726 of the record *Curr\_Record* 721 are respectively set as the local variables *Curr\_Name*, *Curr\_Min* and *Curr\_Max*.
- 15 • At step 2405, a test is performed to check if the local variable *Curr\_Name* is equal to the function parameter *ST\_Name*. If it is the case, then control is given to step 2409; otherwise control is given to step 2406.
- At step 2406, a test is performed to check if the record 721 *Curr\_Record* is the last record of the STT table 720. If it is the case, then control is given to step 2408; otherwise control is given to step 2407.
- 20 • At step 2407, the record following *Curr\_Record* in the STT table 720 becomes the new record 721 *Curr\_Record*. Then control is given to step 2404.
- At step 2408, the local variable *STI\_Row* is set equal to the value 0 (zero). Then control is given to step 2412.
- 25 • At step 2409, the range of cells pointed by the description Ptr field 724 of the record 721 *Curr\_Record* is set as *STDT\_address*.
- At step 2410, the local variable *Element\_Nbr* is set equal to the input parameter *STI\_Element*, upper bounded by the local variable *Curr\_Max*, and minored by the local variable *Curr\_Min*.
- 30 • At step 2411, the local variable *STI\_row* is set equal to the number of rows of the range of cells *STDT\_address*, incremented by the value of the local variable *STI\_Element*, and decremented by 1 (one).
- At step 2412, the execution of the *STI\_row* function completes as control is returned to the function caller.
- 35 • At step 2421, the second method is in its default state, waiting for a call to the *STI\_Col* function.
- At step 2422, the *STI\_Col* function call is detected, as a result of a user action. The function is called with one parameter named *ST\_Name*.
- At step 2423, the first record 721 of the STT table 720 is set as *Curr\_Record*.
- 40 • At step 2424, the field Name 722 of the record *Curr\_Record* 721 is set as the local variables *Curr\_Name*.
- At step 2425, a test is performed to check if the local variable *Curr\_Name* is equal to the function parameter *ST\_Name*. If it is the case, then control is given to step 2429; otherwise control is given to step 2426.
- 45 • At step 2426, a test is performed to check if the record 721 *Curr\_Record* is the last record of the STT table 720. If it is the case, then control is given to step 2428; otherwise control is given to step 2427.
- At step 2427, the record following *Curr\_Record* in the STT table 720 becomes the new record 721 *Curr\_Record*. Then control is given to step 2424.
- 50 • At step 2428, the local variable *STI\_Row* is set equal to the value 0 (zero). Then control is given to step 2431.
- At step 2429, the range of cells pointed by the description Ptr field 724 of the record 721 *Curr\_Record* is set as *STDT\_address*.

- At step 2430, the local variable *STI\_col* is set equal to the number of columns of the range of cells *STDT\_adress*.
- At step 2431, the execution of the *STI\_col* function completes as control is returned to the function caller.

#### ~~5~~ **ALTERNATE EMBODIMENTS**

The methods and systems according to the present invention may be used advantageously in those environments where elements of information are organized as vertically structured two dimensions tables.

- 10 The methods and systems according to the present invention may be used advantageously in those environments where elements of information are organized as multidimensional tables having more than two dimensions.

While the invention has been particularly shown and described with reference to a preferred embodiment, it will be understood that various changes in form and detail may be made therein without departing from the spirit, and scope of the invention.

**Claims**

What is claimed is:

1. A method, in a multi-dimensional electronic data table comprising a plurality of data, for managing deletion operations in a recursive scalable template instance; a recursive scalable  
5 template instance comprising a variable number of contiguous recursive element instances ordered and aligned along a first data table dimension and structured according to a recursive scalable template; said recursive scalable template comprising a recursive element including one or a plurality of scalable templates; each recursive element instance having a variable size along said first data table dimension and a same size along a second  
10 data table dimension; a recursive element instance comprising one or a plurality of scalable template instances; each scalable template instance of each recursive element instance being aligned along said first data table dimension; each scalable template instance within each recursive element instance being aligned along a second data table dimension; a scalable template instance comprising a variable number of elements structured according  
15 to a scalable template; an element being defined as a range of data; a range of data comprising one or a plurality of data; said method comprising the steps of:
  - detecting a delete command for deleting one or a plurality of contiguous elements selected in a scalable template instance of a recursive element instance;
  - identifying :
    - 20 • the scalable template instance where to delete said one or a plurality of selected elements;
    - the one or plurality of selected elements, in the scalable template instance, to delete;
    - the scalable template associated with said scalable template instance;
  - identifying :
    - 25 • the recursive scalable template instance and the recursive element instance comprising the identified scalable template instance;
    - deleting in the identified scalable template instance, the one or a plurality of selected elements; all remaining elements of the identified scalable template instance remaining contiguous;
    - 30 • adjusting the size of the identified recursive element instance along said first data table dimension according to the size of the largest scalable template instance in said recursive element instance; all remaining recursive element instances of the identified recursive scalable template instance remaining contiguous.
2. The method according to the preceding claim wherein said recursive scalable template  
35 instance further comprises a header part and/or a footer part; the header part of the recursive scalable template comprising a predefined number of recursive meta-elements; the footer part of the scalable template comprising a predefined number of recursive meta-elements; a recursive meta-element comprising one or a plurality of scalable templates; said method comprising the further steps of :
  - 40 • detecting a delete command for deleting one or a plurality of contiguous elements selected in a scalable template instance of a recursive meta-element instance;
  - identifying :
    - the scalable template instance where to delete said one or a plurality of selected elements;
    - 45 • the one or plurality of selected elements in the scalable template instance;
    - the scalable template associated with said scalable template instance;
  - identifying :
    - the recursive scalable template instance and the recursive meta-element instance comprising the identified scalable template instance;
    - 50 • deleting in the identified scalable template instance, the one or a plurality of selected elements; all remaining elements of the identified scalable template instance remaining contiguous;

- adjusting the size of the identified recursive meta-element instance along said first data table dimension according to the size of the largest scalable template instance in said recursive meta-element instance; all remaining recursive element instances and recursive meta-element instances of the identified recursive scalable template instance remaining contiguous.
- 5
3. The method according to any one of the preceding claims comprising the further steps of:
    - detecting a delete command for deleting in a recursive scalable template instance, one or a plurality of selected contiguous recursive element instances;
    - identifying :
      - 10 • the recursive scalable template instance where to delete said one or a plurality of recursive element instances;
      - the one or plurality of recursive element instances to delete in the recursive scalable template instance;
      - 15 • the recursive scalable template associated with said recursive scalable template instance;
    - deleting in the recursive scalable template instance, the one or a plurality of selected contiguous recursive element instances; all remaining recursive element instances of the identified recursive scalable template instance remaining contiguous.
  4. The method according to any one of the preceding claims comprising the further steps of:
    - 20 • preventing the deletion in a recursive scalable template instance, of one or a plurality of recursive meta-element instances.
  5. The method according to any one of the preceding claims comprising the further steps of:
    - detecting a delete command for deleting a recursive scalable template instance;
    - 25 • identifying said recursive scalable template instance and the recursive scalable template associated with said recursive scalable template instance;
    - deleting said recursive scalable template instance.
  6. The method according to any one of the preceding claims wherein said step in a recursive scalable template instance of deleting one or a plurality of contiguous elements in a scalable template instance, or of deleting one or a plurality of contiguous recursive
    - 30 element instances, comprises the further step of :
      - determining whether this deletion corrupts any other existing recursive scalable template instance in the data table or not, a recursive scalable template instance being corrupted when the recursive element instances are no longer structured according to the associated recursive scalable template.
  - 35 7. The method according to the preceding claim wherein said step of determining whether the deletion corrupts any other existing recursive scalable template instance in the data table or not, comprises the further step of:
    - cancelling the deletion if the deletion corrupts any recursive scalable template instance defined as being a critical instance.
  - 40 8. The method according to the preceding claim comprising, for each recursive scalable template instance, the step of:
    - defining each of said one or plurality of recursive scalable template instances as being a critical instance or a not critical instance.
  9. The method according to any one of the preceding claims wherein said step in a
    - 45 recursive scalable template instance of deleting one or a plurality of contiguous elements in a scalable template instance, or of deleting one or a plurality of contiguous recursive element instances, comprises the further step of :
      - determining whether this deletion corrupts any other existing scalable template instance in the data table or not, a scalable template instance being corrupted when the elements are no longer structured according to the associated scalable template.
  - 50 10. The method according to the preceding claim wherein said step of determining whether the deletion corrupts any other existing scalable template instance in the data table or not, comprises the further step of:

- cancelling the deletion if the deletion corrupts any scalable template instance defined as being a critical instance.
11. The method according to any one of the preceding claims wherein said multidimensional electronic data table is an electronic spreadsheet comprising a plurality of cells identified by a cell address along each dimension.
12. The method according to the preceding claim wherein a scalable template instance comprises a variable number of contiguous elements of same size ordered and aligned along a given spreadsheet dimension and structured according to a scalable template; an element being defined as a range of cells; said scalable template comprising an element format and/or an element profile; an element format defining for each cell within each element, one or a plurality of format attributes; an element profile defining a cell content and a cell destination for each cell within each element; said cell destination specifying whether the cell is an input cell for receiving an entry or an output cell for producing a result.
13. The method according to the preceding claim wherein the step of deleting in the identified scalable template instance, one or a plurality of selected elements; all remaining elements of the identified scalable template instance remaining contiguous, comprises the further step of :
- structuring each output cell of each remaining element of the scalable template instance according to the element profile defined in the scalable template;
  - maintaining unchanged the content of each input cell of each remaining element within the scalable template instance.
14. A system comprising means adapted for carrying out the steps of the method according to any one of the preceding claims.
15. A computer program comprising instructions for carrying out the steps of the method according to any one of claims 1 to 13, when said computer program is executed.



## SYSTEM AND METHOD IN A DATA TABLE FOR MANAGING DELETION OPERATIONS IN RECURSIVE SCALABLE TEMPLATE INSTANCES

### *Abstract*

The present invention is directed to a method, system and program in a multi-dimensional  
5 electronic data table comprising a plurality of data, for managing deletion operations in a  
recursive scalable template instance; a recursive scalable template instance comprising a  
variable number of contiguous recursive element instances ordered and aligned along a first  
data table dimension and structured according to a recursive scalable template; said  
10 recursive scalable template comprising a recursive element including one or a plurality of  
scalable templates; each recursive element instance having a variable size along said first  
data table dimension and a same size along a second data table dimension; a recursive  
element instance comprising one or a plurality of scalable template instances; each scalable  
template instance of each recursive element instance being aligned along said first data  
15 table dimension; each scalable template instance within each recursive element instance  
being aligned along a second data table dimension; a scalable template instance comprising  
a variable number of elements structured according to a scalable template; an element  
being defined as a range of data; a range of data comprising one or a plurality of data.

Figure 17A

1/23




Fig. 1A




Fig. 1B




Fig. 2

2/23




Fig. 3




Fig. 4




Fig. 5






Fig. 6

**Fig. 7A**



**Fig. 7B**



**Fig. 7C**




Fig. 7D




Fig. 7E






Fig. 14B







7/23




Fig. 8

8/23




Fig. 9

9/23




Fig. 10

10/23




Fig. 11

11/23




Fig. 12



12/23

**Fig. 13A**

1312 1313 1314 1315

1300

1301

1302

1303

1304

1305

1306

1307

1308

1309


1310

1311

New Instance: Template Name  
Element ID: Control ID

Create Cancel

New Instance Top Left	NO	Critical Instance Lost	Other Instance Lost	Data Lost
Overlay	YES	YES	YES	
Horizontal Insert	NO	NO	YES	
Horizontal Insert by Range	NO	NO	YES	
Vertical Insert	YES	YES	YES	
Vertical Insert by Range	YES	YES	YES	



Recursive Scalable Template Instance Descriptor Table

**Fig. 19F**

2276	2277	2278	2279	2280	2281	2282	2270
STI_col	STI_row	STI_name	Container_col	Container_row	Container_range	STI_rec_ptr	
2274	//		//				2271
2273							2272





Fig. 14A

14/23

1800



**Fig. 15 A**




Fig. 15 B

Fig. 16A

Fig. 16A is a software dialog box. It contains the following elements:

- Fields for "Current Instance" and "Template Name" (labeled 1908 and 1909).
- A "Deleted Element ID" field (labeled 1910).
- A "Critical" checkbox (labeled 1911).
- "Delete" and "Cancel" buttons (labeled 1901 and 1902).
- "Selection too far" and "Selection outside block" buttons (labeled 1903).
- Four radio button options:
  - "Delete all fields in selected range" (labeled 1905)
  - "Delete all fields in selected row" (labeled 1906)
  - "Delete selected elements" (labeled 1912)
  - "Delete selected instance" (labeled 1913)
- "YES" and "NO" buttons (labeled 1904 and 1907).

Fig. 16B

Fig. 16B is a software dialog box. It contains the following elements:

- "Current Instance" field set to "None" (labeled 1929).
- "Delete" and "Cancel" buttons (labeled 1920 and 1921).
- A table of options (labeled 1923 and 1924):
 

	Content Delete	Horizontal Delete	Horizontal Delete by Range	Vertical Delete	Vertical Delete by Range	Data Lost
1930	NO	NO	NO	YES	YES	YES
1928	NO	NO	NO	YES	YES	YES
1927	NO	NO	NO	YES	YES	YES
1926	YES	YES	YES	YES	YES	YES
1925	YES	YES	YES	YES	YES	YES

Fig. 16C

Fig. 16C is a software dialog box. It contains the following elements:

- "Recursive Scalable Template Name" field (labeled 1950).
- "Cancel" and "Delete" buttons (labeled 1940 and 1941).
- A list of radio button options:
  - "Delete all fields in selected range" (labeled 1949)
  - "Delete all fields in selected elements of current Scalable Template Instance" (labeled 1948)
  - "Delete all fields in current Scalable Template Instance" (labeled 1947)
  - "Delete selected elements in current Scalable Template Instance" (labeled 1946)
  - "Delete Scalable Template Instance(s) in current container" (labeled 1945)
  - "Delete Recursive Scalable Template Instance(s) in container comprising STP" (labeled 1944)

17/23




Fig. 17A




Fig. 17B



18/23

Fig. 18A





Fig. 18B










Fig. 20A

Figure 20A shows a software interface for creating or editing a template instance. The interface includes a title bar (2300) and a main content area (2311). The content area contains several input fields and buttons:

- Recursive Global Template Name:** A text input field (2301).
- Number of Recursive Elements:** A numeric input field (2302).
- Warnings:** A section containing four checkboxes (2303):
  - FST Instance too wide:** A checkbox (2304).
  - FST Instance too high:** A checkbox (2305).
  - FST Instance unbalanced:** A checkbox (2306).
  - FST Instance violates existing data:** A checkbox (2307).
- Buttons:** At the bottom, there are three buttons: **Create Instance** (2310), **Create instance with new sheet** (2309), and **Cancel** (2308).

Fig. 20B

Figure 20B shows a software interface for editing a template instance. The interface includes a title bar (2321) and a main content area (2322). The content area contains several input fields and buttons:

- Done:** A button (2323).
- Save:** A button (2333).
- Save As:** A button (2332).
- Element:** A radio button (2331).
- Meta-Element:** A radio button (2330).
- Number of fields:** A numeric input field (2327).
- Field Rank:** A numeric input field (2335).
- Field Template:** A text input field (2334).
- MRE Header:** A text input field (2324).
- Field Template:** A text input field (2328).

22/23




Fig. 20C

23/23

Fig. 21A





Fig. 21B





PCT/EP2004/003049



**This Page is Inserted by IFW Indexing and Scanning  
Operations and is not part of the Official Record**

**BEST AVAILABLE IMAGES**

Defective images within this document are accurate representations of the original documents submitted by the applicant.

Defects in the images include but are not limited to the items checked:

- ☐ BLACK BORDERS
- ☐ IMAGE CUT OFF AT TOP, BOTTOM OR SIDES
- ☒ FADED TEXT OR DRAWING
- ☒ BLURRED OR ILLEGIBLE TEXT OR DRAWING
- ☐ SKEWED/SLANTED IMAGES
- ☐ COLOR OR BLACK AND WHITE PHOTOGRAPHS
- ☐ GRAY SCALE DOCUMENTS
- ☒ LINES OR MARKS ON ORIGINAL DOCUMENT
- ☐ REFERENCE(S) OR EXHIBIT(S) SUBMITTED ARE POOR QUALITY
- ☐ OTHER: \_\_\_\_\_

**IMAGES ARE BEST AVAILABLE COPY.**

**As rescanning these documents will not correct the image problems checked, please do not report these problems to the IFW Image Problem Mailbox.**